



MOSEK Optimization Server

Release 8.0.0.81

MOSEK ApS

2017

1	Introduction	1
1.1	Why the Optimization Server?	1
1.2	License agreement	1
2	Installation	3
2.1	What's in the box	3
2.2	Requirements	3
2.3	Installation	3
2.4	Running the Server	4
2.5	OptServer Options	4
3	Overview	7
3.1	Synchronous Optimization	7
3.2	Asynchronous Optimization	8
4	Guidelines	11
4.1	Known Limitations	11
4.2	Resources and performance	11
4.3	The license system	12
5	Tutorials	13
5.1	Synchronous Problem Submission	13
5.2	Asynchronous Problem Submission	15
5.3	Problem Submission via Condor	17
6	Security	19
6.1	User role management	19
7	Configuration	21
8	Web GUI interface	23
8.1	Login page	23
8.2	Job list page	23
8.3	User Page	26
9	OptServer Reference	29
9.1	OptServer protocol	29
9.2	Parameters	30
9.3	Response codes	78
9.4	Enumerations	99
10	Supported File Formats	127
10.1	The LP File Format	128
10.2	The MPS File Format	133
10.3	The OPF Format	145
10.4	The CBF Format	154

10.5	The XML (OSiL) Format	169
10.6	The Task Format	169
10.7	The JSON Format	169
10.8	The Solution File Format	176
Bibliography		179
API Index		181

INTRODUCTION

The **MOSEK** Optimization Suite 8.0.0.81 is a powerful software package capable of solving large-scale optimization problems of the following kind:

- linear,
- convex quadratic,
- conic quadratic (also known as second-order cone),
- semidefinite,
- and general convex.

Integer constrained variables are supported for all problem classes except for semidefinite and general convex problems. In order to obtain an overview of features in the **MOSEK** Optimization Suite consult the [product introduction](#) guide.

1.1 Why the Optimization Server?

The OptServer makes it easy to offload heavy computations to a remote machine. This is useful for running **MOSEK** on a wider range of devices.

1.2 License agreement

Before using the **MOSEK** software, please read the license agreement available in the distribution at <MSKHOME>/mosek/8/mosek-eula.pdf or on the **MOSEK** website <https://mosek.com/sales/license-agreement>.

MOSEK uses some third-party open-source libraries. Their license details follows.

zlib

MOSEK includes the *zlib* library obtained from the [zlib website](#). The license agreement for *zlib* is shown in [Listing 1.1](#).

Listing 1.1: *zlib* license.

```
zlib.h -- interface of the 'zlib' general purpose compression library
version 1.2.7, May 2nd, 2012

Copyright (C) 1995-2012 Jean-loup Gailly and Mark Adler

This software is provided 'as-is', without any express or implied
warranty. In no event will the authors be held liable for any damages
arising from the use of this software.
```

Permission is granted to anyone to use this software for any purpose, including commercial applications, and to alter it and redistribute it freely, subject to the following restrictions:

1. The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required.
2. Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software.
3. This notice may not be removed or altered from any source distribution.

Jean-loup Gailly
jloup@gzip.org

Mark Adler
madler@alumni.caltech.edu

fplib

MOSEK includes the floating point formatting library developed by David M. Gay obtained from the [netlib website](#). The license agreement for *fplib* is shown in [Listing 1.2](#).

Listing 1.2: *fplib* license.

```
/*
 *
 * The author of this software is David M. Gay.
 *
 * Copyright (c) 1991, 2000, 2001 by Lucent Technologies.
 *
 * Permission to use, copy, modify, and distribute this software for any
 * purpose without fee is hereby granted, provided that this entire notice
 * is included in all copies of any software which is or includes a copy
 * or modification of this software and in all copies of the supporting
 * documentation for such software.
 *
 * THIS SOFTWARE IS BEING PROVIDED "AS IS", WITHOUT ANY EXPRESS OR IMPLIED
 * WARRANTY. IN PARTICULAR, NEITHER THE AUTHOR NOR LUCENT MAKES ANY
 * REPRESENTATION OR WARRANTY OF ANY KIND CONCERNING THE MERCHANTABILITY
 * OF THIS SOFTWARE OR ITS FITNESS FOR ANY PARTICULAR PURPOSE.
 *
 */
```

INSTALLATION

2.1 What's in the box

The **MOSEK** OptServer is shipped as part of the **MOSEK** Optimization Suite. It is located in the folder *MSKHOME/mosek/8/opt-server*, where *MSKHOME* is the folder **MOSEK** has been installed in.

The OptServer files are organized in the following folders:

- **bin** – It contains the executables. i.e.
 - *MosekServer*, see Section 2.4.
 - *install_MosekServer*, see Section 2.1.
- **var** – It contains the working directories and the GUI elements:
- **etc** – It contains default configuration file and security key.

2.2 Requirements

OptServer only requires Python 3+ to run the configuration script. It has been tested only on Linux 64 bit.

2.3 Installation

To install the OptServer you need to execute the *install_MosekServer* located in the *MSKDIR/opt-server/* folder. A set of options can be provided to customize the installation:

```
--inplace
    Set up the server to run directly in the unpacked distro directory

--user
    Install in ~/.local

--global
    Install in /usr

--prefix DIR
    Install in DIR

--certdir DIR
    This directory contains valid cert.pem and key.pem for HTTPS. If DIR='', then HTTPS is disabled.

--password PWD
    Password for initial user admin

--port PORT
    Configure server to listen to port PORT
```

`--disable-gui`
Disable GUI and API

`--enable-get`
Enable fetching submitted data/problem files

`--enable-anonymous`
Enable submitting without credentials

If the installation succeeds, you can then run the OptServer as described in Section 2.4.

2.4 Running the Server

The OptServer can be started by running the executable `MosekServer` from the `OPT_SERVER_HOME/bin` folder, for instance

```
$ $OPT_SERVER_HOME/bin/MosekServer
```

With no command line the server runs using the configurations setup during the installation process, see Section 2.1. To override the configuration set in the installation, several options can be passed to the server.

Note: Options can be prefixed by a single or a double dash, i.e. either `-` or `--`.

Some examples follow.

Switching debug mode on

If the server is not working as expected, it may be useful to turn on debugging:

```
MosekServer -debug=true
```

Change the port

Changing the port is a pretty standard step.

```
MosekServer --port=30080
```

2.5 OptServer Options

The complete list of options follow.

`-base={/var/Mosek/server}`
Base directory

`-certdir=/etc/Mosek/server/cert`
Enable SSL, `cert.pem` and `key.pem` in this directory

`-cmd=$basedir/script/solve.py $workdir $task`
Solver command

`-config=/etc/Mosek/server.conf`
Specify configuration file (JSON)

`-debug=false`
Turn on debugging info (turned off by default). This is a boolean option.

`-enable-anonymous-submit=false`
Enable anonymous submitting (turned off by default).

`-enable-get-problem=false`
Enable fetching submitted tasks (turned off by default).

`-enable-user-api=false`
Enable extended programming API

`-enable-user-gui=false`
Enable user interface (turned off by default).

`-hostname=hostname`
Server host name

`-logfile=filename`
Log file name

`-login-expiry=86400`
Login expiry time in seconds

`-port=30080`
Port to listen to

`-staticdir=extern`
Directory with files served under `/static/`

OVERVIEW

In this section an overview of the basic concepts about the OptServer is given.


- *Synchronous Job submission*
- *Asynchronous Job submission*

3.1 Synchronous Optimization

The easiest way to submit optimization problem to the OptServer is in *synchronous mode*:

1. A submission request is sent over the OptServer and the problem is transferred.
2. The submitter is put on hold.
3. The OptServer runs the optimizer and wait for the results.
4. When the optimizer terminates the OptServer collects the outcome and passes over the client.
5. The client receives the solution and get back control.

The process can be represented as in Fig. 3.1.



The workflow is simple and effective for problems that does not take long to solve, or at least in all settings in which the client can wait for the job to complete.


Warning: If the connection between the client and the OptServer is lost, the job result can only be recovered by manually accessing the job workspace on the server.

3.2 Asynchronous Optimization

The OptServer accepts jobs in *asynchronous mode*, i.e. once the job request is accepted, the client get control back and the server proceed with the optimization. The client can query the OptServer for the status of the job and in case retrieve the solution, if any. The steps can be summarized as:

1. A submission request is sent over the OptServer and the problem is transferred.
2. The submitter regain control and can continue its execution flow.
3. The client can query the OptServer at any time about the job status and solution availability.
4. The OptServer runs the optimizer and wait for the results.
5. When the optimizer terminates the OptServer collects the outcome.

The process can be represented as in Fig. 3.2.



Asynchronous mode is particularly suitable when

- a job is expected to run for long time,
- one must submit a set of small jobs that can run in parallel or
- the submitter is a short-lived process, such as a *docker instance*.

Warning: The OptServer does not implement any queing strategy, so a job is executed as it is submitted.

GUIDELINES

4.1 Known Limitations

The main limitation in the use of the **MOSEK** Optimization Server 8.0.0.81 are reported in this section.

Platforms

Currently the **MOSEK** OptServer has been only tested on Linux 64bit machines.

Compatibility

Job submission using **MOSEK** API is only available starting from **MOSEK** 8.

Submitting jobs directly using HTTP commands is possible as long as the file format is accepted. However, it must be noticed that the compatibility does not depend on the OptServer but on the underlying **MOSEK** solver available on server machine.

4.2 Resources and performance

OptServer is a very lightweight server and requires very limited resources both in terms of memory and CPU.

CPU/Memory

The use of CPU/memory resources by OptServer should be negligible.

Network

Most of the network load is due to the transfer of the optimization problem from the client to the server. That happens in a single burst. Therefore

- For long running jobs the transfer time is typically negligible,
- For easy to solve problems the transfer time may be more significant.

Hint: The same problem can result in file of different sizes depending on the chosen format.

However, OptServer has not been designed for time critical production environment.

Disk usage

Each job is stored on disk along with log and solutions. The reasons are:

1. avoid to keep jobs in memory while the solver is running,
2. in case of crash, information can be recovered from the disk,
3. solution and result can be recovered asynchronously reading from disk.

Therefore a suitable amount of free space must be available.

The folder used to store jobs information is under the *basedir* folder, that can be set in the configuration file.

Note: OptServer does not delete data for completed jobs. Users of cloud services should take some care in case they pay storage fees.

4.3 The license system

MOSEK is a commercial product that **always** needs a valid license to work. A license is typically provided as a license file that allows the user to access the subset of the **MOSEK** Optimization Suite functionalities it is entitled for, and for the right amount of time. **MOSEK** uses a third party license manager to implement license checking.

By default a license token remains checked out for the duration of the **MOSEK** session, i.e.

To change the license systems behavior to returning the license token after each call to **MOSEK** set the parameter *MSK_IPAR_CACHE_LICENSE* to *MSK_OFF*.

4.3.1 Waiting for a free license

By default an error will be returned if no license token is available. By setting the parameter *MSK_IPAR_LICENSE_WAIT* **MOSEK** can be instructed to wait until a license token is available.

4.3.2 Manually stopping the license system

TUTORIALS

This section contains tutorials that illustrate how communicate with the **MOSEK** OptServer in order to

- offload optimization problem from the client to the server and
- retrieve the solution and the solver log.

The tutorials are implemented using the Python 3 programming language. The reason for this choice is that Python provides an easy-to-use HTTP client and allows for a simple and compact code.

- *Submission and solution in synchronous mode*
- *Submission and solution in asynchronous mode*
- *Submission and solution using Condor*

5.1 Synchronous Problem Submission

This tutorial shows how to

- submit a job to the OptServer,
- remotely run **MOSEK** and wait for the optimization to terminate and
- retrieve the solution and log.

The optimization problem is assumed to be stored in a file using one of the available *file format*.

The connection is managed using the `http` Python module, and it is assumed to be established successfully: as a result, an object `con` is available to manage the connection.

First of all, the problem is submitted to the OptServer by a *submit* command

Listing 5.1: How to submit a job to the OptServer.

```
con.request("POST", '/submit', dataf)
resp = con.getresponse()
```

If no errors have occurred, a request for running the optimizer can be sent

Listing 5.2: How to run an optimization job with OptServer.

```
con.request("GET", "/solve?token="+token)
resp = con.getresponse()
```

At this point the request will return when the optimization terminates. If no errors have happened, the results are already available

Listing 5.3: How to get the results.

```
res = resp.getheader('X-Mosek-Res-Code',None)
trm = resp.getheader('X-Mosek-Trm-Code',None)

print("\tMOSEK response: %s" % res)
print("\t\ttrm resp: %s" % trm)
if resp.status == http.client.OK:
    print("Solution:")
    print(resp.read().decode('ascii',errors='ignore'))
```

The log is readily available as well

Listing 5.4: How to retrieve the log for a job on OptServer.

```
con.request("GET", "/log?token="+token)
resp = con.getresponse()
```

The whole example is in [Listing 5.5](#).

Listing 5.5: How to submit a job and solve the problem synchronously.

```
import http.client
import sys

def check_status(resp):

    print("\tHTTPResponse: %s / %s" % (resp.status,resp.reason))
    for k,v in resp.getheaders():
        print("\t%s: %s" % (k,v))

    if resp.status not in [http.client.OK, http.client.NO_CONTENT]:
        print("An error occurred!")
        sys.exit(1)

if __name__ == '__main__':
    host = sys.argv[1]
    port = int(sys.argv[2])
    probfile = sys.argv[3]

    con = http.client.HTTPConnection(host,port)
    try:
        with open(probfile,'rb') as dataf:
            ## Submit job
            print("POST /submit")

            con.request("POST", '/submit', dataf)
            resp = con.getresponse()
            check_status(resp)

            token = resp.read().decode('ascii')

            ## Solve and wait for solution
            print("GET /solve")
            con.request("GET", "/solve?token="+token)
            resp = con.getresponse()
            check_status(resp)
            res = resp.getheader('X-Mosek-Res-Code',None)
            trm = resp.getheader('X-Mosek-Trm-Code',None)
```

1 0 1

1. 2. 3.

```
print("\tMOSEK response: %s" % res)
print("\t      trm resp: %s" % trm)
if resp.status == http.client.OK:
    print("Solution:")
    print(resp.read().decode('ascii', errors='ignore'))
```

The log is readily available as well

Listing 5.9: How to retrieve the log for a job on OptServer.

```
con.request("GET", "/log?token="+token)
resp = con.getresponse()

if resp.status == http.client.OK:
    print(resp.read().decode('utf-8', errors='ignore'))
```

The whole example is in Listing 5.10.

Listing 5.10: How to submit a job and solve the problem asynchronously.

```
import http.client
import sys

def check_status(resp):

    print("\tHTTPResponse: %s / %s" % (resp.status,resp.reason))
    for k,v in resp.getheaders():
        print("\t%s: %s" % (k,v))

    if resp.status not in [http.client.OK, http.client.NO_CONTENT]:
        print("An error occurred!")
        sys.exit(1)

if __name__ == '__main__':
    host = sys.argv[1]
    port = int(sys.argv[2])

    probfile = sys.argv[3]

    token=[]
    con = http.client.HTTPConnection(host,port)
    try:
        with open(probfile,'rb') as dataf:
            ## Submit job
            print("POST /submit")
            con.request("POST", '/submit', dataf)
            resp = con.getresponse()
            check_status(resp)

            token = resp.read().decode('ascii')

            ## Start solving end close connection
            print("GET /solve-background")
            con.request("GET", "/solve-background?token="+token)
            resp = con.getresponse()
            check_status(resp)

    finally:
        con.close()
        print("connection closed")

    con = http.client.HTTPConnection(host,port)
```

```

print("connection open")

try:
    print("GET /solution")
    con.request("GET", "/solution?token="+token)
    resp = con.getresponse()

    check_status(resp)

    res = resp.getheader('X-Mosek-Res-Code', None)
    trm = resp.getheader('X-Mosek-Trm-Code', None)

    print("\tMOSEK response: %s" % res)
    print("\t      trm resp: %s" % trm)
    if resp.status == http.client.OK:
        print("Solution:")
        print(resp.read().decode('ascii', errors='ignore'))

    print("GET /log")
    con.request("GET", "/log?token="+token)
    resp = con.getresponse()

    if resp.status == http.client.OK:
        print(resp.read().decode('utf-8', errors='ignore'))
finally:
    con.close()

```

5.3 Problem Submission via Condor

HTCondor, formerly known as *Condor* is

“a specialized workload management system for compute-intensive jobs.”

This tutorial shows how to submit optimization problem to a *HTCondor* server via OptServer.

The idea is very simple: since OptServer executes **MOSEK** using a simple Python script (`solve.py`), we can instruct OptServer to use a different script that will interface with *HTCondor*. To this extent we use the script as in Listing 5.11.

Listing 5.11: An example of script to off-load a job from OptServer to a *HTCondor* server.

```

1 import sys
2 import os, os.path
3 import subprocess
4
5 if __name__ == '__main__':
6     workdir = sys.argv[1]
7     probfile = sys.argv[2]
8     pidfile = os.path.join(workdir, "PID")
9
10    with open(pidfile, 'wt', encoding='ascii') as f:
11        f.write(str(os.getpid))
12
13    r = 1
14    try:
15        r = subprocess.call(['condor_run',
16                             os.path.abspath(os.path.join(os.path.dirname(__file__), "solve.py")),
17                             workdir,
18                             probfile,
19                             '-noPID'])

```

```
20     finally:
21         try:
22             os.remove(pidfile)
23         except:
24             pass
25
26 sys.exit(r)
```

The script operates as follows:

- lines 10–11: the job PID is stored in a text file called PID in the working directory;
- lines 14–24 : a *HTCondor* process is created, responsible to run the `solve.py` script.

To tell OptServer to use the script in [Listing 5.11](#) instead of the default `solve.py`, the `cmd` option (see [Section 7](#)) in the configuration file `server.conf` must be modified accordingly. In this case the script is available in the `script` directory of the OptServer distribution. Therefore the configuration file can be simply modified changing the `cmd` option to

```
"cmd"      : "${CONFIGDIR}/script/tocondor.py ${TASK}",
```

SECURITY

OptServer uses on HTTPS by default, for which a self-signed demo certificate is provided in `security/cert`. The user can point OptServer to another certificate setting the `certdir` option (see Section 7).

6.1 User role management

Users can be *registered* or *anonymous*. A registered user can be either

- *administrator* or
- *submitter* or
- *anonymous*.

Users can be added, removed or their status changed from the web interface (see Section 8).

Administrator

An administrator can submit jobs and perform all administrative tasks.

It is also possible to grant temporary *administrator* access. Any *administrator* can log in the web interface and grant a access token to a user, from the *tokens* page. Each temporary token is specified in terms of how long it lasts.

Submitter

This users can both submit jobs and access the web interface to

- collect information about their own jobs,
- modify their own information but
- they can not perform administrative task.

Anonymous

Anonymous users are not allowed by default, unless the `enable-anonymous-submit` is specified. Anonymous users can only submit jobs.

CONFIGURATION

The configuration of the OptServer is stored in a single flat JSON file. Following keys are recognized:

address `<string>`
Host and port, in the format `HOST:PORT`. If `HOST` is left blank then `localhost` is used

basedir `<string>`
Work directory.

certdir `<string>`
Directory containing `key.pem` and `cert.pem`.

externdir `<string>`
Directory containing passive files (css, javascript, images etc.) that is required by the web pages

enable-login `<true|false>`
Enable login and management.

enable-management `<true|false>`
Enable management, even when login is disabled. Forced to `true` if `enable-login` is `true`

enable-anonymous-submit `<true|false>`
Allow submitting tasks without authentication.

login-expiry `<integer>`
Expiry of login session in seconds.

password-salt `<string>`
Name of the file used for password salting.

cmd `<string>`
The command executed to solve problems.

The `cmd` key allows for variable substitution using `${...}`. Following variables are recognized:

- ***BASEDIR***
- ***CONFIGDIR***
- ***TASK*** Name of the problem file.
- ***WORKDIR*** Name of the working directory for the task.

If a key is not specified, then its default value, if any, is used.

The default configuration is stored in the `server.conf` file and reported in [Listing 7.1](#).

Listing 7.1: The OptServer default configuration.

```
{
  "address"      : ":30080",
  "basedir"      : "run",
  "externdir"    : "../management/extern",
  "logfile"      : "run/server.log",
  "pidfile"      : "run/PID",
  "cmd"          : "${CONFIGDIR}/script/solve.py ${TASK}",
}
```

```
"enable-login" : true,  
"certdir"      : "security/cert",  
"password-salt" : "./run/salt"  
}
```

WEB GUI INTERFACE

The **MOSEK** OptServer provides a minimalistic web interface that allows to

- monitor and terminate jobs and
- grant or revoke access tokens,

The web interface can be activated setting the options `enable-management` or `enable-login` (see Section 7). By default is not active.

8.1 Login page

When the user opens the web interface a login page is shown. The user must input its user name and in order to be authenticated. See Section 6 for further details.




Fig. 8.1: A screenshot of the login page.

Note: The OptServer does not keep trace of login attempts.

If the login is successful the user is presented with a minimal login page.




Fig. 8.2: A screenshot of the main page.

8.2 Job list page

Selecting the **All Jobs** or **My Jobs** link from the left sidebar for administrators and submitters respectively, the job list page is visualize. It provides information about jobs and for submitters the possibility to post a new job.

An example of how the page looks like is in Fig. 8.3.




Fig. 8.3: A screenshot of the job list page.

8.2.1 The Job List

The list contains all jobs that have been submitted by the user if it a submitter, or all users for administrators. For each job the following information are available

- **Job ID:** a unique job id,
- **Description:** the submitted file name,
- **Owner:** the user that submit the job (left blank if anonymous),
- **Status:** whether the job is running, complete with success or something went wrong,
- **Submitted:** when the job has been submitted,
- **Duration:** the overall duration of the job.

For each job two buttons are available that will provide additional information directly from the solver execution:

- **Log:** shows the solver log for that job,
- **Solution:** the solution for the job.

Note: **Log** and **Solution** are displayed in a new window.

8.2.2 Job List Filter

To navigate among the submitted jobs OptServer provides a simple search tool that combines criteria from two fields:

- **Filter Search :** Entries in the text search box are matched against values in the columns “Job ID”, “Description”, “Owner” and “Status”. If the string is a substring in any of those fields the row is a match.
- **Date Search :** The entry should either be a single data or a date range (“start .. end”). A date is written as

December 21 2012 12:45:00
 2012-12-21 12:45:00

and the various parts can be left out, i.e. the following are valid

Dec 21 2012 meaning Dec 21 2012 00:00:00
 2012 meaning Jan 1 2012 00:00:00

Ranges are specified with the .., and either end can be left blank to indicate no bound, e.g.

Dec 21 2012 .. meaning Dec 21 2012 00:00:00 until now
 .. -2012 meaning anything before Jan 1 2012 00:00:00
 2011..2012 meaning anything btween Jan 1 2011 and Jan 1 2012

Some examples follow

All jobs submitted in May 2016

In the *Date Search* field enter

All jobs submitted by users with name john

In the *Filter Text* field input

All failed jobs

In the *Filter Text* field input

8.2.3 Job submission

If the user is a *submitter* it can directly submit a job in asynchronous mode using the GUI.

8.2.4 Job Status

The possible job statuses are listed in [Table 8.1](#).

Table 8.1: Status keys.

Status key	Description
<i>submitted</i>	The job has just been submitted, waiting to run.
<i>running</i>	The job is currently running.
<i>failed</i>	The solver did not terminated correctly.
<i>done</i>	The solver terminated correctly with a response code.

Details follow.

Status *submitted*

The *submitted* status indicates that the job has been received and stored. It is in the process to be executed.

Note: OptServer does not provide any queing system. Therefore a job is never waiting for execution.

Status *running*

A job is *running* when the solver has been started but not yet terminated.

Status *failed*

The *failed* status indicates that something wrong has happened. Two scenarios apply:

1. The running script returned an error before the solvr could start.
2. The solver did started, but it terminated unexpectedly and providing no error code. This is the situation for instance in which a serious bug leads to a *segmentation fault*. The *log* may provide useful information on the reason the crash happend.

Tip: Please consider making a bug report whenever a job fails.

Status *done*

Whenever the job terminates in a nice and controlled way it is flagged as *done*. This *does not* implies the optimization has been successful, but only that the solver has terminated its execution and returned a response code. To distinguish among the different scenarios OptServer also provides the solver response code, which clearly informs the user how and why the solver stopped.

For example

- *MSK_RES_OK (0)* indicates the solver terminate successfully,
- *MSK_RES_ERR_LICENSE_EXPIRED (1001)* indicates the **MOSEK** license has expired,
- *MSK_RES_TRM_MAX_TIME (10001)* indicates the solver termianted because the maximum allowed time has reached.

The log contains more detailed information.

8.3 User Page

In this page OptServer list its users, organized in a sortable table that report

- the username
- the full name,
- the email and
- the roles.

To get more information about the roles see Section 6.

In this page administrators can:

- list the OptServer users,
- delete/create users and
- update user information.

An example of how the page looks like is in Fig. 8.4.



Fig. 8.4: A screenshot of the user page.

Add New User

A new user can be add using the form on top of the page. Compulsory fields are

- **Login,**
- **Password.**

A user is by default neither an administrator nor a submitter.

Modify an Existing User

Administrators can modify the user information by editing the relevant fields directly in the user list: just click with mouse pointer and edit!

Delete an Existing User

An existing user can be delete only by an administrator. This operation will not completely wipe out the user from the OptServer:

- the job submitted by the user will still be listed,
- all temporary files stored (problems and their log and solutions) will not be deleted.

Warning: If a new user with the same login name is created, it will take over all data from the deleted user!

OPTSERVER REFERENCE

9.1 OptServer protocol

The server protocol is HTTP plus a couple of extension headers. Commands that the client can use:

`POST /api/submit`

Post a problem to the server.

On response OK, a token identifying the problem is returned in the response body, and the token cookie is set to the token string. If logins are disabled or anonymous submits are allowed, no authentication is required. Otherwise, one of following is required:

- An access token, passed in the query part as `access-token=...`, or
- a valid session, passed in the session cookie (i.e. a user that is logged in can submit).

`GET /api/solve`

Start solving and wait for the solver to finish.

The token is passed either as a query string `token=<tokenstr>`, or in the token cookie. The Accept header identifies the accepted solution formats. Currently recognized formats are:

<code>application/x-mosek-task</code>	Request solution in <code>.task</code> format.
<code>application/x-mosek-json</code>	Request solution in JSON format.
<code>text/plain</code>	Request a plain ASCII formatted solution

`GET /api/solve-background`

Start solving the identified task in background, return immediately.

It returns OK is the solver started successfully. The token is passed either as a query string `token=<tokenstr>`, or in the token cookie.

`GET /api/log`

Return the log.

The token is passed either as a query string `token=<tokenstr>`, or in the token cookie. If the query string contains the parameter `offset=XXXX`, the log file will be returned from offset `XXXX`.

GET /api/solution

Return the solution

It returns the solution if available, or NO_CONTENT if the task exists but no solution is available. The token is passed either as a query string `token=<tokenstr>`, or in the token cookie.

HEAD /api/break

Attempt to terminate the solver.

The token is passed either as a query string `token=<tokenstr>`, or in the token cookie.

9.2 Parameters

All parameters (alphabetical order)

- *double parameters*
- *integer parameters*
- *string parameters*

Parameters grouped by topic

Note: some parameters may appear in more than one group.

- *Dual simplex optimizer*
- *Logging*
- *Analysis*
- *Basis identification*
- *Overall solver*
- *Data check*
- *Presolve*
- *Termination criterion*
- *Infeasibility report*
- *Data input/output*
- *Interior-point method*
- *Debugging*
- *Solution input/output*
- *Progress call-back*
- *Conic interior-point method*
- *Simplex optimizer*
- *Primal simplex optimizer*
- *Mixed-integer optimization*
- *Optimization system*
- *License manager*

- *Output information*
- *Nonlinear convex method*

9.2.1 Parameters List (alphabetically)

Double Parameters

MSK_DPAR_ANA_SOL_INFEAS_TOL

If a constraint violates its bound with an amount larger than this value, the constraint name, index and violation will be printed by the solution analyzer.

Accepted Values: [0.0 ;+inf]

Default Value: 1e-6

Groups: *Analysis*

MSK_DPAR_BASIS_REL_TOL_S

Maximum relative dual bound violation allowed in an optimal basic solution.

Accepted Values: [0.0 ;+inf]

Default Value: 1.0e-12

Groups: *Simplex optimizer, Termination criterion*

MSK_DPAR_BASIS_TOL_S

Maximum absolute dual bound violation in an optimal basic solution.

Accepted Values: [1.0e-9 ;+inf]

Default Value: 1.0e-6

Groups: *Simplex optimizer, Termination criterion*

MSK_DPAR_BASIS_TOL_X

Maximum absolute primal bound violation allowed in an optimal basic solution.

Accepted Values: [1.0e-9 ;+inf]

Default Value: 1.0e-6

Groups: *Simplex optimizer, Termination criterion*

MSK_DPAR_CHECK_CONVEXITY_REL_TOL

This parameter controls when the full convexity check declares a problem to be non-convex. Increasing this tolerance relaxes the criteria for declaring the problem non-convex.

A problem is declared non-convex if negative (positive) pivot elements are detected in the Cholesky factor of a matrix which is required to be PSD (NSD). This parameter controls how much this non-negativity requirement may be violated.

If d_i is the pivot element for column i , then the matrix Q is considered to not be PSD if:

$$d_i \leq -|Q_{ii}|\text{check_convexity_rel_tol}$$

Accepted Values: [0 ;+inf]

Default Value: 1e-10

Groups: *Interior-point method*

MSK_DPAR_DATA_SYM_MAT_TOL

Absolute zero tolerance for elements in in suymmetric matrixes. If any value in a symmetric matrix is smaller than this parameter in absolute terms **MOSEK** will treat the values as zero and generate a warning.

Accepted Values: [1.0e-16 ;1.0e-6]

Default Value: 1.0e-12

Groups: *Data check*

MSK_DPAR_DATA_SYM_MAT_TOL_HUGE

An element in a symmetric matrix which is larger than this value in absolute size causes an error.

Accepted Values: [0.0 ;+inf]

Default Value: 1.0e20

Groups: *Data check*

MSK_DPAR_DATA_SYM_MAT_TOL_LARGE

An element in a symmetric matrix which is larger than this value in absolute size causes a warning message to be printed.

Accepted Values: [0.0 ;+inf]

Default Value: 1.0e10

Groups: *Data check*

MSK_DPAR_DATA_TOL_AIJ

Absolute zero tolerance for elements in A . If any value A_{ij} is smaller than this parameter in absolute terms **MOSEK** will treat the values as zero and generate a warning.

Accepted Values: [1.0e-16 ;1.0e-6]

Default Value: 1.0e-12

Groups: *Data check*

MSK_DPAR_DATA_TOL_AIJ_HUGE

An element in A which is larger than this value in absolute size causes an error.

Accepted Values: [0.0 ;+inf]

Default Value: 1.0e20

Groups: *Data check*

MSK_DPAR_DATA_TOL_AIJ_LARGE

An element in A which is larger than this value in absolute size causes a warning message to be printed.

Accepted Values: [0.0 ;+inf]

Default Value: 1.0e10

Groups: *Data check*

MSK_DPAR_DATA_TOL_BOUND_INF

Any bound which in absolute value is greater than this parameter is considered infinite.

Accepted Values: [0.0 ;+inf]

Default Value: 1.0e16

Groups: *Data check*

MSK_DPAR_DATA_TOL_BOUND_WRN

If a bound value is larger than this value in absolute size, then a warning message is issued.

Accepted Values: [0.0 ;+inf]

Default Value: 1.0e8

Groups: *Data check*

MSK_DPAR_DATA_TOL_CJ_LARGE

An element in c which is larger than this value in absolute terms causes a warning message to be printed.

Accepted Values: [0.0 ;+inf]

Default Value: 1.0e8

Groups: *Data check*

MSK_DPAR_DATA_TOL_C_HUGE

An element in c which is larger than the value of this parameter in absolute terms is considered to be huge and generates an error.

Accepted Values: [0.0 ;+inf]

Default Value: 1.0e16

Groups: *Data check*

MSK_DPAR_DATA_TOL_QIJ

Absolute zero tolerance for elements in Q matrices.

Accepted Values: [0.0 ;+inf]

Default Value: 1.0e-16

Groups: *Data check*

MSK_DPAR_DATA_TOL_X

Zero tolerance for constraints and variables i.e. if the distance between the lower and upper bound is less than this value, then the lower and upper bound is considered identical.

Accepted Values: [0.0 ;+inf]

Default Value: 1.0e-8

Groups: *Data check*

MSK_DPAR_INTPNT_CO_TOL_DFEAS

Dual feasibility tolerance used by the conic interior-point optimizer.

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-8

Groups: *Interior-point method, Termination criterion, Conic interior-point method*

MSK_DPAR_INTPNT_CO_TOL_INFEAS

Controls when the conic interior-point optimizer declares the model primal or dual infeasible. A small number means the optimizer gets more conservative about declaring the model infeasible.

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-10

Groups: *Interior-point method, Termination criterion, Conic interior-point method*

MSK_DPAR_INTPNT_CO_TOL_MU_RED

Relative complementarity gap feasibility tolerance used by the conic interior-point optimizer.

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-8

Groups: *Interior-point method, Termination criterion, Conic interior-point method*

MSK_DPAR_INTPNT_CO_TOL_NEAR_REL

If **MOSEK** cannot compute a solution that has the prescribed accuracy, then it will multiply the termination tolerances with value of this parameter. If the solution then satisfies the termination criteria, then the solution is denoted near optimal, near feasible and so forth.

Accepted Values: [1.0 ;+inf]

Default Value: 1000

Groups: *Interior-point method, Termination criterion, Conic interior-point method*

MSK_DPAR_INTPNT_CO_TOL_PFEAS

Primal feasibility tolerance used by the conic interior-point optimizer.

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-8

Groups: *Interior-point method, Termination criterion, Conic interior-point method*

MSK_DPAR_INTPNT_CO_TOL_REL_GAP

Relative gap termination tolerance used by the conic interior-point optimizer.

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-7

Groups: *Interior-point method, Termination criterion, Conic interior-point method*

MSK_DPAR_INTPNT_NL_MERIT_BAL

Controls if the complementarity and infeasibility is converging to zero at about equal rates.

Accepted Values: [0.0 ;0.99]

Default Value: 1.0e-4

Groups: *Interior-point method, Nonlinear convex method*

MSK_DPAR_INTPNT_NL_TOL_DFEAS

Dual feasibility tolerance used when a nonlinear model is solved.

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-8

Groups: *Interior-point method, Termination criterion, Nonlinear convex method*

MSK_DPAR_INTPNT_NL_TOL_MU_RED

Relative complementarity gap tolerance.

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-12

Groups: *Interior-point method, Termination criterion, Nonlinear convex method*

MSK_DPAR_INTPNT_NL_TOL_NEAR_REL

If the **MOSEK** nonlinear interior-point optimizer cannot compute a solution that has the prescribed accuracy, then it will multiply the termination tolerances with value of this parameter. If the solution then satisfies the termination criteria, then the solution is denoted near optimal, near feasible and so forth.

Accepted Values: [1.0 ;+inf]

Default Value: 1000.0

Groups: *Interior-point method, Termination criterion, Nonlinear convex method*

MSK_DPAR_INTPNT_NL_TOL_PFEAS

Primal feasibility tolerance used when a nonlinear model is solved.

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-8

Groups: *Interior-point method, Termination criterion, Nonlinear convex method*

MSK_DPAR_INTPNT_NL_TOL_REL_GAP

Relative gap termination tolerance for nonlinear problems.

Accepted Values: [1.0e-14 ;+inf]

Default Value: 1.0e-6

Groups: *Termination criterion, Interior-point method, Nonlinear convex method*

MSK_DPAR_INTPNT_NL_TOL_REL_STEP

Relative step size to the boundary for general nonlinear optimization problems.

Accepted Values: [1.0e-4 ;0.9999999]

Default Value: 0.995

Groups: *Interior-point method, Nonlinear convex method*

MSK_DPAR_INTPNT_QO_TOL_DFEAS

Dual feasibility tolerance used when the interior-point optimizer is applied to a quadratic optimization problem..

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-8

Groups: *Interior-point method, Termination criterion*

MSK_DPAR_INTPNT_QO_TOL_INFEAS

Controls when the conic interior-point optimizer declares the model primal or dual infeasible. A small number means the optimizer gets more conservative about declaring the model infeasible.

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-10

Groups: *Interior-point method, Termination criterion*

MSK_DPAR_INTPNT_QO_TOL_MU_RED

Relative complementarity gap feasibility tolerance used when interior-point optimizer is applied to a quadratic optimization problem.

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-8

Groups: *Interior-point method, Termination criterion*

MSK_DPAR_INTPNT_QO_TOL_NEAR_REL

If **MOSEK** cannot compute a solution that has the prescribed accuracy, then it will multiply the termination tolerances with value of this parameter. If the solution then satisfies the termination criteria, then the solution is denoted near optimal, near feasible and so forth.

Accepted Values: [1.0 ;+inf]

Default Value: 1000

Groups: *Interior-point method, Termination criterion*

MSK_DPAR_INTPNT_QO_TOL_PFEAS

Primal feasibility tolerance used when the interior-point optimizer is applied to a quadratic optimization problem.

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-8

Groups: *Interior-point method, Termination criterion*

MSK_DPAR_INTPNT_QO_TOL_REL_GAP

Relative gap termination tolerance used when the interior-point optimizer is applied to a quadratic optimization problem.

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-8

Groups: *Interior-point method, Termination criterion*

MSK_DPAR_INTPNT_TOL_DFEAS

Dual feasibility tolerance used for linear and quadratic optimization problems.

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-8

Groups: *Interior-point method, Termination criterion*

MSK_DPAR_INTPNT_TOL_DSAFE

Controls the initial dual starting point used by the interior-point optimizer. If the interior-point optimizer converges slowly and/or the constraint or variable bounds are very large, then it might be worthwhile to increase this value.

Accepted Values: [1.0e-4 ;+inf]

Default Value: 1.0

Groups: *Interior-point method*

MSK_DPAR_INTPNT_TOL_INFEAS

Controls when the optimizer declares the model primal or dual infeasible. A small number means the optimizer gets more conservative about declaring the model infeasible. A value of 0.0 means the optimizer must have an exact certificate of infeasibility and this is very unlikely to happen.

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-10

Groups: *Interior-point method, Termination criterion, Nonlinear convex method*

MSK_DPAR_INTPNT_TOL_MU_RED

Relative complementarity gap tolerance.

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-16

Groups: *Interior-point method, Termination criterion*

MSK_DPAR_INTPNT_TOL_PATH

Controls how close the interior-point optimizer follows the central path. A large value of this parameter means the central is followed very closely. On numerical unstable problems it may be worthwhile to increase this parameter.

Accepted Values: [0.0 ;0.9999]

Default Value: 1.0e-8

Groups: *Interior-point method*

MSK_DPAR_INTPNT_TOL_PFEAS

Primal feasibility tolerance used for linear and quadratic optimization problems.

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-8

Groups: *Interior-point method, Termination criterion*

MSK_DPAR_INTPNT_TOL_PSAFE

Controls the initial primal starting point used by the interior-point optimizer. If the interior-point optimizer converges slowly and/or the constraint or variable bounds are very large, then it may be worthwhile to increase this value.

Accepted Values: [1.0e-4 ;+inf]

Default Value: 1.0

Groups: *Interior-point method*

MSK_DPAR_INTPNT_TOL_REL_GAP

Relative gap termination tolerance.

Accepted Values: [1.0e-14 ;+inf]

Default Value: 1.0e-8

Groups: *Termination criterion, Interior-point method*

MSK_DPAR_INTPNT_TOL_REL_STEP

Relative step size to the boundary for linear and quadratic optimization problems.

Accepted Values: [1.0e-4 ;0.999999]

Default Value: 0.9999

Groups: *Interior-point method*

MSK_DPAR_INTPNT_TOL_STEP_SIZE

If the step size falls below the value of this parameter, then the interior-point optimizer assumes that it is stalled. In other words the interior-point optimizer does not make any progress and therefore it is better stop.

Accepted Values: [0.0 ;1.0]

Default Value: 1.0e-6

Groups: *Interior-point method*

MSK_DPAR_LOWER_OBJ_CUT

If either a primal or dual feasible solution is found proving that the optimal objective value is outside, the interval [*MSK_DPAR_LOWER_OBJ_CUT*, *MSK_DPAR_UPPER_OBJ_CUT*], then **MOSEK** is terminated.

Accepted Values: [-inf ;+inf]

Default Value: -1.0e30

Groups: *Termination criterion*

MSK_DPAR_LOWER_OBJ_CUT_FINITE_TRH

If the lower objective cut is less than the value of this parameter value, then the lower objective cut i.e. *MSK_DPAR_LOWER_OBJ_CUT* is treated as $-\infty$.

Accepted Values: [-inf ;+inf]

Default Value: -0.5e30

Groups: *Termination criterion*

MSK_DPAR_MIO_DISABLE_TERM_TIME

This parameter specifies the number of seconds n during which the termination criteria governed by

- *MSK_IPAR_MIO_MAX_NUM_RELAXS*
- *MSK_IPAR_MIO_MAX_NUM_BRANCHES*
- *MSK_DPAR_MIO_NEAR_TOL_ABS_GAP*
- *MSK_DPAR_MIO_NEAR_TOL_REL_GAP*

is disabled since the beginning of the optimization.

A negative value is identical to infinity i.e. the termination criteria are never checked.

Accepted Values: [-inf ;+inf]

Default Value: -1.0

Groups: *Mixed-integer optimization, Termination criterion*

MSK_DPAR_MIO_MAX_TIME

This parameter limits the maximum time spent by the mixed-integer optimizer. A negative number means infinity.

Accepted Values: $[-\text{inf}; +\text{inf}]$

Default Value: -1.0

Groups: *Mixed-integer optimization, Termination criterion*

MSK_DPAR_MIO_NEAR_TOL_ABS_GAP

Relaxed absolute optimality tolerance employed by the mixed-integer optimizer. This termination criteria is delayed. See *MSK_DPAR_MIO_DISABLE_TERM_TIME* for details.

Accepted Values: $[0.0; +\text{inf}]$

Default Value: 0.0

Groups: *Mixed-integer optimization*

MSK_DPAR_MIO_NEAR_TOL_REL_GAP

The mixed-integer optimizer is terminated when this tolerance is satisfied. This termination criteria is delayed. See *MSK_DPAR_MIO_DISABLE_TERM_TIME* for details.

Accepted Values: $[0.0; +\text{inf}]$

Default Value: 1.0e-3

Groups: *Mixed-integer optimization, Termination criterion*

MSK_DPAR_MIO_REL_GAP_CONST

This value is used to compute the relative gap for the solution to an integer optimization problem.

Accepted Values: $[1.0\text{e-}15; +\text{inf}]$

Default Value: 1.0e-10

Groups: *Mixed-integer optimization, Termination criterion*

MSK_DPAR_MIO_TOL_ABS_GAP

Absolute optimality tolerance employed by the mixed-integer optimizer.

Accepted Values: $[0.0; +\text{inf}]$

Default Value: 0.0

Groups: *Mixed-integer optimization*

MSK_DPAR_MIO_TOL_ABS_RELAX_INT

Absolute relaxation tolerance of the integer constraints. I.e. $\min(|x| - \lfloor x \rfloor, \lceil x \rceil - |x|)$ is less than the tolerance then the integer restrictions assumed to be satisfied.

Accepted Values: $[1\text{e-}9; +\text{inf}]$

Default Value: 1.0e-5

Groups: *Mixed-integer optimization*

MSK_DPAR_MIO_TOL_FEAS

Feasibility tolerance for mixed integer solver.

Accepted Values: $[1\text{e-}9; 1\text{e-}3]$

Default Value: 1.0e-6

Groups: *Mixed-integer optimization*

MSK_DPAR_MIO_TOL_REL_DUAL_BOUND_IMPROVEMENT

If the relative improvement of the dual bound is smaller than this value, the solver will terminate the root cut generation. A value of 0.0 means that the value is selected automatically.

Accepted Values: $[0.0; 1.0]$

Default Value: 0.0

Groups: *Mixed-integer optimization*

MSK_DPAR_MIO_TOL_REL_GAP

Relative optimality tolerance employed by the mixed-integer optimizer.

Accepted Values: [0.0 ; +inf]

Default Value: 1.0e-4

Groups: *Mixed-integer optimization, Termination criterion*

MSK_DPAR_OPTIMIZER_MAX_TIME

Maximum amount of time the optimizer is allowed to spent on the optimization. A negative number means infinity.

Accepted Values: [-inf ; +inf]

Default Value: -1.0

Groups: *Termination criterion*

MSK_DPAR_PREOLVE_TOL_ABS_LINDEP

Absolute tolerance employed by the linear dependency checker.

Accepted Values: [0.0 ; +inf]

Default Value: 1.0e-6

Groups: *Presolve*

MSK_DPAR_PREOLVE_TOL_AIJ

Absolute zero tolerance employed for a_{ij} in the presolve.

Accepted Values: [1.0e-15 ; +inf]

Default Value: 1.0e-12

Groups: *Presolve*

MSK_DPAR_PREOLVE_TOL_REL_LINDEP

Relative tolerance employed by the linear dependency checker.

Accepted Values: [0.0 ; +inf]

Default Value: 1.0e-10

Groups: *Presolve*

MSK_DPAR_PREOLVE_TOL_S

Absolute zero tolerance employed for s_i in the presolve.

Accepted Values: [0.0 ; +inf]

Default Value: 1.0e-8

Groups: *Presolve*

MSK_DPAR_PREOLVE_TOL_X

Absolute zero tolerance employed for x_j in the presolve.

Accepted Values: [0.0 ; +inf]

Default Value: 1.0e-8

Groups: *Presolve*

MSK_DPAR_QCQO_REFORMULATE_REL_DROP_TOL

This parameter determines when columns are dropped in incomplete Cholesky factorization during reformulation of quadratic problems.

Accepted Values: [0 ; +inf]

Default Value: 1e-15

Groups: *Interior-point method*

MSK_DPAR_SEMIDEFINITE_TOL_APPROX

Tolerance to define a matrix to be positive semidefinite.

Accepted Values: [1.0e-15 ; +inf]

Default Value: 1.0e-10

Groups: *Data check*

MSK_DPAR_SIMPLEX_ABS_TOL_PIV

Absolute pivot tolerance employed by the simplex optimizers.

Accepted Values: [1.0e-12 ; +inf]

Default Value: 1.0e-7

Groups: *Simplex optimizer*

MSK_DPAR_SIM_LU_TOL_REL_PIV

Relative pivot tolerance employed when computing the LU factorization of the basis in the simplex optimizers and in the basis identification procedure.

A value closer to 1.0 generally improves numerical stability but typically also implies an increase in the computational work.

Accepted Values: [1.0e-6 ; 0.999999]

Default Value: 0.01

Groups: *Basis identification, Simplex optimizer*

MSK_DPAR_UPPER_OBJ_CUT

If either a primal or dual feasible solution is found proving that the optimal objective value is outside, the interval [*MSK_DPAR_LOWER_OBJ_CUT*, *MSK_DPAR_UPPER_OBJ_CUT*], then **MOSEK** is terminated.

Accepted Values: [-inf ; +inf]

Default Value: 1.0e30

Groups: *Termination criterion*

MSK_DPAR_UPPER_OBJ_CUT_FINITE_TRH

If the upper objective cut is greater than the value of this parameter, then the upper objective cut *MSK_DPAR_UPPER_OBJ_CUT* is treated as ∞ .

Accepted Values: [-inf ; +inf]

Default Value: 0.5e30

Groups: *Termination criterion*

Integer Parameters

MSK_IPAR_ANA_SOL_BASIS

Controls whether the basis matrix is analyzed in solution analyzer.

Accepted Values: *MSK_onoffkeye*

Default Value: *MSK_ON*

Groups: *Analysis*

MSK_IPAR_ANA_SOL_PRINT_VIOLATED

Controls whether a list of violated constraints is printed.

All constraints violated by more than the value set by the parameter *MSK_DPAR_ANA_SOL_INFEAS_TOL* will be printed.

Accepted Values: *MSK_onoffkeye*

Default Value: *MSK_OFF*

Groups: *Analysis*

MSK_IPAR_AUTO_SORT_A_BEFORE_OPT

Controls whether the elements in each column of *A* are sorted before an optimization is performed. This is not required but makes the optimization more deterministic.

Accepted Values: *MSK_onoffkeye*

Default Value: *MSK_OFF*

Groups: *Debugging*

MSK_IPAR_AUTO_UPDATE_SOL_INFO

Controls whether the solution information items are automatically updated after an optimization is performed.

Accepted Values: *MSK_onoffkeye*

Default Value: *MSK_OFF*

Groups: *Optimization system*

MSK_IPAR_BASIS_SOLVE_USE_PLUS_ONE

If a slack variable is in the basis, then the corresponding column in the basis is a unit vector with -1 in the right position. However, if this parameter is set to *MSK_ON*, -1 is replaced by 1.

Accepted Values: *MSK_onoffkeye*

Default Value: *MSK_OFF*

Groups: *Simplex optimizer*

MSK_IPAR_BI_CLEAN_OPTIMIZER

Controls which simplex optimizer is used in the clean-up phase.

Accepted Values: *MSK_optimizertypee*

Default Value: *MSK_OPTIMIZER_FREE*

Groups: *Basis identification, Overall solver*

MSK_IPAR_BI_IGNORE_MAX_ITER

If the parameter *MSK_IPAR_INTPNT_BASIS* has the value *MSK_BI_NO_ERROR* and the interior-point optimizer has terminated due to maximum number of iterations, then basis identification is performed if this parameter has the value *MSK_ON*.

Accepted Values: *MSK_onoffkeye*

Default Value: *MSK_OFF*

Groups: *Interior-point method, Basis identification*

MSK_IPAR_BI_IGNORE_NUM_ERROR

If the parameter *MSK_IPAR_INTPNT_BASIS* has the value *MSK_BI_NO_ERROR* and the interior-point optimizer has terminated due to a numerical problem, then basis identification is performed if this parameter has the value *MSK_ON*.

Accepted Values: *MSK_onoffkeye*

Default Value: *MSK_OFF*

Groups: *Interior-point method, Basis identification*

MSK_IPAR_BI_MAX_ITERATIONS

Controls the maximum number of simplex iterations allowed to optimize a basis after the basis identification.

Accepted Values: `[0 ;+inf]`

Default Value: `1000000`

Groups: *Basis identification, Termination criterion*

MSK_IPAR_CACHE_LICENSE

Specifies if the license is kept checked out for the lifetime of the mosek environment (*MSK_ON*) or returned to the server immediately after the optimization (*MSK_OFF*).

By default the license is checked out for the lifetime of the **MOSEK** environment by the first call to the optimizer.

Check-in and check-out of licenses have an overhead. Frequent communication with the license server should be avoided.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *License manager*

MSK_IPAR_CHECK_CONVEXITY

Specify the level of convexity check on quadratic problems

Accepted Values: *MSKcheckconvexitytypee*

Default Value: *MSK_CHECK_CONVEXITY_FULL*

Groups: *Data check, Nonlinear convex method*

MSK_IPAR_COMPRESS_STATFILE

Control compression of stat files.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

MSK_IPAR_INFEAS_GENERIC_NAMES

Controls whether generic names are used when an infeasible subproblem is created.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Infeasibility report*

MSK_IPAR_INFEAS_PREFER_PRIMAL

If both certificates of primal and dual infeasibility are supplied then only the primal is used when this option is turned on.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Overall solver*

MSK_IPAR_INFEAS_REPORT_AUTO

Controls whether an infeasibility report is automatically produced after the optimization if the problem is primal or dual infeasible.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Data input/output, Solution input/output*

MSK_IPAR_INFEAS_REPORT_LEVEL

Controls the amount of information presented in an infeasibility report. Higher values imply more information.

Accepted Values: $[0 ; +\infty]$

Default Value: 1

Groups: *Infeasibility report, Output information*

MSK_IPAR_INTPNT_BASIS

Controls whether the interior-point optimizer also computes an optimal basis.

Accepted Values: *MSKbasindtypee*

Default Value: *MSK_BI_ALWAYS*

Groups: *Interior-point method, Basis identification*

MSK_IPAR_INTPNT_DIFF_STEP

Controls whether different step sizes are allowed in the primal and dual space.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Interior-point method*

MSK_IPAR_INTPNT_HOTSTART

Currently not in use.

Accepted Values: *MSKintpnthotstarte*

Default Value: *MSK_INTPNT_HOTSTART_NONE*

Groups: *Interior-point method*

MSK_IPAR_INTPNT_MAX_ITERATIONS

Controls the maximum number of iterations allowed in the interior-point optimizer.

Accepted Values: $[0 ; +\infty]$

Default Value: 400

Groups: *Interior-point method, Termination criterion*

MSK_IPAR_INTPNT_MAX_NUM_COR

Controls the maximum number of correctors allowed by the multiple corrector procedure. A negative value means that **MOSEK** is making the choice.

Accepted Values: $[-1 ; +\infty]$

Default Value: -1

Groups: *Interior-point method*

MSK_IPAR_INTPNT_MAX_NUM_REFINEMENT_STEPS

Maximum number of steps to be used by the iterative refinement of the search direction. A negative value implies that the optimizer chooses the maximum number of iterative refinement steps.

Accepted Values: $[-\infty ; +\infty]$

Default Value: -1

Groups: *Interior-point method*

MSK_IPAR_INTPNT_MULTI_THREAD

Controls whether the interior-point optimizers are allowed to employ multiple threads if more threads is available.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Optimization system*

MSK_IPAR_INTPNT_OFF_COL_TRH

Controls how many offending columns are detected in the Jacobian of the constraint matrix.

0	no detection
1	aggressive detection
> 1	higher values mean less aggressive detection

Accepted Values: $[0 ; +\infty]$

Default Value: 40

Groups: *Interior-point method*

MSK_IPAR_INTPNT_ORDER_METHOD

Controls the ordering strategy used by the interior-point optimizer when factorizing the Newton equation system.

Accepted Values: *MSKorderingtypee*

Default Value: *MSK_ORDER_METHOD_FREE*

Groups: *Interior-point method*

MSK_IPAR_INTPNT_REGULARIZATION_USE

Controls whether regularization is allowed.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Interior-point method*

MSK_IPAR_INTPNT_SCALING

Controls how the problem is scaled before the interior-point optimizer is used.

Accepted Values: *MSKscalingtypee*

Default Value: *MSK_SCALING_FREE*

Groups: *Interior-point method*

MSK_IPAR_INTPNT_SOLVE_FORM

Controls whether the primal or the dual problem is solved.

Accepted Values: *MSKsolveforme*

Default Value: *MSK_SOLVE_FREE*

Groups: *Interior-point method*

MSK_IPAR_INTPNT_STARTING_POINT

Starting point used by the interior-point optimizer.

Accepted Values: *MSKstartpointtypee*

Default Value: *MSK_STARTING_POINT_FREE*

Groups: *Interior-point method*

MSK_IPAR_LICENSE_DEBUG

This option is used to turn on debugging of the license manager.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *License manager*

MSK_IPAR_LICENSE_PAUSE_TIME

If *MSK_IPAR_LICENSE_WAIT* = *MSK_ON* and no license is available, then **MOSEK** sleeps a number of milliseconds between each check of whether a license has become free.

Accepted Values: [0 ;1000000]

Default Value: 100

Groups: *License manager*

MSK_IPAR_LICENSE_SUPPRESS_EXPIRE_WRNS

Controls whether license features expire warnings are suppressed.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *License manager, Output information*

MSK_IPAR_LICENSE_TRH_EXPIRY_WRN

If a license feature expires in a numbers days less than the value of this parameter then a warning will be issued.

Accepted Values: [0 ;+inf]

Default Value: 7

MSK_IPAR_LICENSE_WAIT

If all licenses are in use **MOSEK** returns with an error code. However, by turning on this parameter **MOSEK** will wait for an available license.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Overall solver, Optimization system, License manager*

MSK_IPAR_LOG

Controls the amount of log information. The value 0 implies that all log information is suppressed. A higher level implies that more information is logged.

Please note that if a task is employed to solve a sequence of optimization problems the value of this parameter is reduced by the value of *MSK_IPAR_LOG_CUT_SECOND_OPT* for the second and any subsequent optimizations.

Accepted Values: [0 ;+inf]

Default Value: 10

Groups: *Output information, Logging*

MSK_IPAR_LOG_ANA_PRO

Controls amount of output from the problem analyzer.

Accepted Values: [0 ;+inf]

Default Value: 1

Groups: *Analysis, Logging*

MSK_IPAR_LOG_BI

Controls the amount of output printed by the basis identification procedure. A higher level implies that more information is logged.

Accepted Values: [0 ;+inf]

Default Value: 4

Groups: *Basis identification, Output information, Logging*

MSK_IPAR_LOG_BI_FREQ

Controls how frequent the optimizer outputs information about the basis identification and how frequent the user-defined call-back function is called.

Accepted Values: [0 ;+inf]

Default Value: 2500

Groups: *Basis identification, Output information, Logging*

MSK_IPAR_LOG_CHECK_CONVEXITY

Controls logging in convexity check on quadratic problems. Set to a positive value to turn logging on. If a quadratic coefficient matrix is found to violate the requirement of PSD (NSD) then a list of negative (positive) pivot elements is printed. The absolute value of the pivot elements is also shown.

Accepted Values: [0 ;+inf]

Default Value: 0

Groups: *Data check, Nonlinear convex method*

MSK_IPAR_LOG_CUT_SECOND_OPT

If a task is employed to solve a sequence of optimization problems, then the value of the log levels is reduced by the value of this parameter. E.g *MSK_IPAR_LOG* and *MSK_IPAR_LOG_SIM* are reduced by the value of this parameter for the second and any subsequent optimizations.

Accepted Values: [0 ;+inf]

Default Value: 1

Groups: *Output information, Logging*

MSK_IPAR_LOG_EXPAND

Controls the amount of logging when a data item such as the maximum number constraints is expanded.

Accepted Values: [0 ;+inf]

Default Value: 0

Groups: *Output information, Logging*

MSK_IPAR_LOG_FACTOR

If turned on, then the factor log lines are added to the log.

Accepted Values: [0 ;+inf]

Default Value: 1

Groups: *Output information, Logging*

MSK_IPAR_LOG_FEAS_REPAIR

Controls the amount of output printed when performing feasibility repair. A value higher than one means extensive logging.

Accepted Values: [0 ;+inf]

Default Value: 1

Groups: *Output information, Logging*

MSK_IPAR_LOG_FILE

If turned on, then some log info is printed when a file is written or read.

Accepted Values: [0 ;+inf]

Default Value: 1

Groups: *Data input/output, Output information, Logging*

MSK_IPAR_LOG_HEAD

If turned on, then a header line is added to the log.

Accepted Values: [0 ;+inf]

Default Value: 1

Groups: *Output information, Logging*

MSK_IPAR_LOG_INFEAS_ANA

Controls amount of output printed by the infeasibility analyzer procedures. A higher level implies that more information is logged.

Accepted Values: [0 ;+inf]

Default Value: 1

Groups: *Infeasibility report, Output information, Logging*

MSK_IPAR_LOG_INTPNT

Controls amount of output printed by the interior-point optimizer. A higher level implies that more information is logged.

Accepted Values: [0 ;+inf]

Default Value: 4

Groups: *Interior-point method, Output information, Logging*

MSK_IPAR_LOG_MIO

Controls the log level for the mixed-integer optimizer. A higher level implies that more information is logged.

Accepted Values: [0 ;+inf]

Default Value: 4

Groups: *Mixed-integer optimization, Output information, Logging*

MSK_IPAR_LOG_MIO_FREQ

Controls how frequent the mixed-integer optimizer prints the log line. It will print line every time *MSK_IPAR_LOG_MIO_FREQ* relaxations have been solved.

Accepted Values: [-inf ;+inf]

Default Value: 10

Groups: *Mixed-integer optimization, Output information, Logging*

MSK_IPAR_LOG_OPTIMIZER

Controls the amount of general optimizer information that is logged.

Accepted Values: [0 ;+inf]

Default Value: 1

Groups: *Output information, Logging*

MSK_IPAR_LOG_ORDER

If turned on, then factor lines are added to the log.

Accepted Values: [0 ;+inf]

Default Value: 1

Groups: *Output information, Logging*

MSK_IPAR_LOG_PRESOLVE

Controls amount of output printed by the presolve procedure. A higher level implies that more information is logged.

Accepted Values: [0 ;+inf]

Default Value: 1

Groups: *Interior-point method, Logging*

MSK_IPAR_LOG_RESPONSE

Controls amount of output printed when response codes are reported. A higher level implies that more information is logged.

Accepted Values: [0 ;+inf]

Default Value: 0

Groups: *Output information, Logging*

MSK_IPAR_LOG_SENSITIVITY

Controls the amount of logging during the sensitivity analysis.

0.Means no logging information is produced.

1.Timing information is printed.

2.Sensitivity results are printed.

Accepted Values: [0 ;+inf]

Default Value: 1

Groups: *Output information, Logging*

MSK_IPAR_LOG_SENSITIVITY_OPT

Controls the amount of logging from the optimizers employed during the sensitivity analysis. 0 means no logging information is produced.

Accepted Values: [0 ;+inf]

Default Value: 0

Groups: *Output information, Logging*

MSK_IPAR_LOG_SIM

Controls amount of output printed by the simplex optimizer. A higher level implies that more information is logged.

Accepted Values: [0 ;+inf]

Default Value: 4

Groups: *Simplex optimizer, Output information, Logging*

MSK_IPAR_LOG_SIM_FREQ

Controls how frequent the simplex optimizer outputs information about the optimization and how frequent the user-defined call-back function is called.

Accepted Values: [0 ;+inf]

Default Value: 1000

Groups: *Simplex optimizer, Output information, Logging*

MSK_IPAR_LOG_SIM_MINOR

Currently not in use.

Accepted Values: [0 ;+inf]

Default Value: 1

Groups: *Simplex optimizer, Output information*

MSK_IPAR_LOG_STORAGE

When turned on, **MOSEK** prints messages regarding the storage usage and allocation.

Accepted Values: [0 ;+inf]

Default Value: 0

Groups: *Output information, Optimization system, Logging*

MSK_IPAR_MAX_NUM_WARNINGS

Each warning is shown a limit number times controlled by this parameter. A negative value is identical to infinite number of times.

Accepted Values: `[-inf ; +inf]`

Default Value: `10`

Groups: *Output information*

MSK_IPAR_MIO_BRANCH_DIR

Controls whether the mixed-integer optimizer is branching up or down by default.

Accepted Values: *MSKbranchdire*

Default Value: *MSK_BRANCH_DIR_FREE*

Groups: *Mixed-integer optimization*

MSK_IPAR_MIO_CONSTRUCT_SOL

If set to *MSK_ON* and all integer variables have been given a value for which a feasible mixed integer solution exists, then **MOSEK** generates an initial solution to the mixed integer problem by fixing all integer values and solving the remaining problem.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Mixed-integer optimization*

MSK_IPAR_MIO_CUT_CLIQUE

Controls whether clique cuts should be generated.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Mixed-integer optimization*

MSK_IPAR_MIO_CUT_CMIR

Controls whether mixed integer rounding cuts should be generated.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Mixed-integer optimization*

MSK_IPAR_MIO_CUT_GMI

Controls whether GMI cuts should be generated.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Mixed-integer optimization*

MSK_IPAR_MIO_CUT_IMPLIED_BOUND

Controls whether implied bound cuts should be generated.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Mixed-integer optimization*

MSK_IPAR_MIO_CUT_KNAPSACK_COVER

Controls whether knapsack cover cuts should be generated.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Mixed-integer optimization*

MSK_IPAR_MIO_CUT_SELECTION_LEVEL

Controls how aggressively generated cuts are selected to be included in the relaxation.

-1. The optimizer chooses the level of cut selection

0. Generated cuts less likely to be added to the relaxation

1. Cuts are more aggressively selected to be included in the relaxation

Accepted Values: `[-1 ; +1]`

Default Value: `-1`

Groups: *Mixed-integer optimization*

MSK_IPAR_MIO_HEURISTIC_LEVEL

Controls the heuristic employed by the mixed-integer optimizer to locate an initial good integer feasible solution. A value of zero means the heuristic is not used at all. A larger value than 0 means that a gradually more sophisticated heuristic is used which is computationally more expensive. A negative value implies that the optimizer chooses the heuristic. Normally a value around 3 to 5 should be optimal.

Accepted Values: `[-inf ; +inf]`

Default Value: `-1`

Groups: *Mixed-integer optimization*

MSK_IPAR_MIO_MAX_NUM_BRANCHES

Maximum number of branches allowed during the branch and bound search. A negative value means infinite.

Accepted Values: `[-inf ; +inf]`

Default Value: `-1`

Groups: *Mixed-integer optimization, Termination criterion*

MSK_IPAR_MIO_MAX_NUM_RELAXS

Maximum number of relaxations allowed during the branch and bound search. A negative value means infinite.

Accepted Values: `[-inf ; +inf]`

Default Value: `-1`

Groups: *Mixed-integer optimization*

MSK_IPAR_MIO_MAX_NUM_SOLUTIONS

The mixed-integer optimizer can be terminated after a certain number of different feasible solutions has been located. If this parameter has the value $n > 0$, then the mixed-integer optimizer will be terminated when n feasible solutions have been located.

Accepted Values: `[-inf ; +inf]`

Default Value: `-1`

Groups: *Mixed-integer optimization, Termination criterion*

MSK_IPAR_MIO_MODE

Controls whether the optimizer includes the integer restrictions when solving a (mixed) integer optimization problem.

Accepted Values: *MSKmiomodee*

Default Value: *MSK_MIO_MODE_SATISFIED*

Groups: *Overall solver*

MSK_IPAR_MIO_MT_USER_CB

It true user callbacks are called from each thread used by this optimizer. If false the user callback is only called from a single thread.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Optimization system*

MSK_IPAR_MIO_NODE_OPTIMIZER

Controls which optimizer is employed at the non-root nodes in the mixed-integer optimizer.

Accepted Values: *MSKoptimizertypee*

Default Value: *MSK_OPTIMIZER_FREE*

Groups: *Mixed-integer optimization*

MSK_IPAR_MIO_NODE_SELECTION

Controls the node selection strategy employed by the mixed-integer optimizer.

Accepted Values: *MSKmionodeseltypee*

Default Value: *MSK_MIO_NODE_SELECTION_FREE*

Groups: *Mixed-integer optimization*

MSK_IPAR_MIO_PERSPECTIVE_REFORMULATE

Enables or disables perspective reformulation in presolve.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Mixed-integer optimization*

MSK_IPAR_MIO_PROBING_LEVEL

Controls the amount of probing employed by the mixed-integer optimizer in presolve.

-1. The optimizer chooses the level of probing employed

0. Probing is disabled

1. A low amount of probing is employed

2. A medium amount of probing is employed

3. A high amount of probing is employed

Accepted Values: *[-inf ; +inf]*

Default Value: *-1*

Groups: *Mixed-integer optimization*

MSK_IPAR_MIO_RINS_MAX_NODES

Controls the maximum number of nodes allowed in each call to the RINS heuristic. The default value of -1 means that the value is determined automatically. A value of zero turns off the heuristic.

Accepted Values: *[-1 ; +inf]*

Default Value: *-1*

Groups: *Mixed-integer optimization*

MSK_IPAR_MIO_ROOT_OPTIMIZER

Controls which optimizer is employed at the root node in the mixed-integer optimizer.

Accepted Values: *MSKoptimizertypee*

Default Value: *MSK_OPTIMIZER_FREE*

Groups: *Mixed-integer optimization*

MSK_IPAR_MIO_ROOT_REPEAT_PREOLVE_LEVEL

Controls whether presolve can be repeated at root node.

- 1 The optimizer chooses whether presolve is repeated
- 0 Never repeat presolve
- 1 Always repeat presolve

Accepted Values: [-1 ;1]

Default Value: -1

Groups: *Mixed-integer optimization*

MSK_IPAR_MIO_VB_DETECTION_LEVEL

Controls how much effort is put into detecting variable bounds.

- 1. The optimizer chooses
 - 0.No variable bounds are detected
 - 1.Only detect variable bounds that are directly represented in the problem
 - 2.Detect variable bounds in probing

Accepted Values: [-1 ;+2]

Default Value: -1

Groups: *Mixed-integer optimization*

MSK_IPAR_MT_SPINCOUNT

Set the number of iterations to spin before sleeping.

Accepted Values: [0 ;1000000000]

Default Value: 0

Groups: *Optimization system*

MSK_IPAR_NUM_THREADS

Controls the number of threads employed by the optimizer. If set to 0 the number of threads used will be equal to the number of cores detected on the machine.

Accepted Values: [0 ;+inf]

Default Value: 0

Groups: *Optimization system*

MSK_IPAR_OPF_MAX_TERMS_PER_LINE

The maximum number of terms (linear and quadratic) per line when an OPF file is written.

Accepted Values: [0 ;+inf]

Default Value: 5

Groups: *Data input/output*

MSK_IPAR_OPF_WRITE_HEADER

Write a text header with date and **MOSEK** version in an OPF file.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output*

MSK_IPAR_OPF_WRITE_HINTS

Write a hint section with problem dimensions in the beginning of an OPF file.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output*

MSK_IPAR_OPF_WRITE_PARAMETERS
Write a parameter section in an OPF file.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Data input/output*

MSK_IPAR_OPF_WRITE_PROBLEM
Write objective, constraints, bounds etc. to an OPF file.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output*

MSK_IPAR_OPF_WRITE_SOLUTIONS
Enable inclusion of solutions in the OPF files.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Data input/output*

MSK_IPAR_OPF_WRITE_SOL_BAS
If *MSK_IPAR_OPF_WRITE_SOLUTIONS* is *MSK_ON* and a basic solution is defined, include the basic solution in OPF files.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output*

MSK_IPAR_OPF_WRITE_SOL_ITG
If *MSK_IPAR_OPF_WRITE_SOLUTIONS* is *MSK_ON* and an integer solution is defined, write the integer solution in OPF files.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output*

MSK_IPAR_OPF_WRITE_SOL_ITR
If *MSK_IPAR_OPF_WRITE_SOLUTIONS* is *MSK_ON* and an interior solution is defined, write the interior solution in OPF files.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output*

MSK_IPAR_OPTIMIZER
The parameter controls which optimizer is used to optimize the task.

Accepted Values: *MSKoptimizertypee*

Default Value: *MSK_OPTIMIZER_FREE*

Groups: *Overall solver*

MSK_IPAR_PARAM_READ_CASE_NAME
If turned on, then names in the parameter file are case sensitive.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output*

MSK_IPAR_PARAM_READ_IGN_ERROR

If turned on, then errors in parameter settings is ignored.

Accepted Values: *MSKOnoffkeye*

Default Value: *MSK_OFF*

Groups: *Data input/output*

MSK_IPAR_PREOLVE_ELIMINATOR_MAX_FILL

Controls the maximum amount of fill-in that can be created by one pivot in the elimination phase of the presolve. A negative value means the parameter value is selected automatically.

Accepted Values: $[-inf ; +inf]$

Default Value: -1

Groups: *Presolve*

MSK_IPAR_PREOLVE_ELIMINATOR_MAX_NUM_TRIES

Control the maximum number of times the eliminator is tried.

Accepted Values: $[-inf ; +inf]$

Default Value: -1

Groups: *Presolve*

MSK_IPAR_PREOLVE_LEVEL

Currently not used.

Accepted Values: $[-inf ; +inf]$

Default Value: -1

Groups: *Overall solver, Presolve*

MSK_IPAR_PREOLVE_LINDEP_ABS_WORK_TRH

The linear dependency check is potentially computationally expensive.

Accepted Values: $[-inf ; +inf]$

Default Value: 100

Groups: *Presolve*

MSK_IPAR_PREOLVE_LINDEP_REL_WORK_TRH

The linear dependency check is potentially computationally expensive.

Accepted Values: $[-inf ; +inf]$

Default Value: 100

Groups: *Presolve*

MSK_IPAR_PREOLVE_LINDEP_USE

Controls whether the linear constraints are checked for linear dependencies.

Accepted Values: *MSKOnoffkeye*

Default Value: *MSK_ON*

Groups: *Presolve*

MSK_IPAR_PREOLVE_MAX_NUM_REDUCTIONS

Controls the maximum number of reductions performed by the presolve. The value of the parameter is normally only changed in connection with debugging. A negative value implies that an infinite number of reductions are allowed.

Accepted Values: $[-inf ; +inf]$

Default Value: -1

MSK_IPAR_PRESOLVE_USE

Controls whether the presolve is applied to a problem before it is optimized.

Accepted Values: *MSKpresolvemodee*

Default Value: *MSK_PRESOLVE_MODE_FREE*

Groups: *Overall solver, Presolve*

MSK_IPAR_PRIMAL_REPAIR_OPTIMIZER

Controls which optimizer that is used to find the optimal repair.

Accepted Values: *MSKoptimizertypee*

Default Value: *MSK_OPTIMIZER_FREE*

Groups: *Overall solver*

MSK_IPAR_READ_DATA_COMPRESSED

If this option is turned on, it is assumed that the data file is compressed.

Accepted Values: *MSKcompresstypee*

Default Value: *MSK_COMPRESS_FREE*

Groups: *Data input/output*

MSK_IPAR_READ_DATA_FORMAT

Format of the data file to be read.

Accepted Values: *MSKdataformate*

Default Value: *MSK_DATA_FORMAT_EXTENSION*

Groups: *Data input/output*

MSK_IPAR_READ_DEBUG

Turns on additional debugging information when reading files.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Data input/output*

MSK_IPAR_READ_KEEP_FREE_CON

Controls whether the free constraints are included in the problem.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Data input/output*

MSK_IPAR_READ_LP_DROP_NEW_VARS_IN_BOUNDS

If this option is turned on, **MOSEK** will drop variables that are defined for the first time in the bounds section.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Data input/output*

MSK_IPAR_READ_LP_QUOTED_NAMES

If a name is in quotes when reading an LP file, the quotes will be removed.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output*

MSK_IPAR_READ_MPS_FORMAT

Controls how strictly the MPS file reader interprets the MPS format.

Accepted Values: *MSKmpsformat*

Default Value: *MSK_MPS_FORMAT_FREE*

Groups: *Data input/output*

MSK_IPAR_READ_MPS_WIDTH

Controls the maximal number of characters allowed in one line of the MPS file.

Accepted Values: *[80 ;+inf]*

Default Value: *1024*

Groups: *Data input/output*

MSK_IPAR_READ_TASK_IGNORE_PARAM

Controls whether **MOSEK** should ignore the parameter setting defined in the task file and use the default parameter setting instead.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Data input/output*

MSK_IPAR_SENSITIVITY_ALL

Not applicable.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Overall solver*

MSK_IPAR_SENSITIVITY_OPTIMIZER

Controls which optimizer is used for optimal partition sensitivity analysis.

Accepted Values: *MSKoptimizertypee*

Default Value: *MSK_OPTIMIZER_FREE_SIMPLEX*

Groups: *Overall solver, Simplex optimizer*

MSK_IPAR_SENSITIVITY_TYPE

Controls which type of sensitivity analysis is to be performed.

Accepted Values: *MSKsensitivitytypee*

Default Value: *MSK_SENSITIVITY_TYPE_BASIS*

Groups: *Overall solver*

MSK_IPAR_SIM_BASIS_FACTOR_USE

Controls whether a (LU) factorization of the basis is used in a hot-start. Forcing a refactorization sometimes improves the stability of the simplex optimizers, but in most cases there is a performance penalty.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Simplex optimizer*

MSK_IPAR_SIM_DEGEN

Controls how aggressively degeneration is handled.

Accepted Values: *MSKsimdegene*

Default Value: *MSK_SIM_DEGEN_FREE*

Groups: *Simplex optimizer*

MSK_IPAR_SIM_DUAL_CRASH

Controls whether crashing is performed in the dual simplex optimizer.

If this parameter is set to x , then a crash will be performed if a basis consists of more than $(100 - x) \bmod f_v$ entries, where f_v is the number of fixed variables.

Accepted Values: $[0 ; +\infty]$

Default Value: 90

Groups: *Dual simplex optimizer*

MSK_IPAR_SIM_DUAL_PHASEONE_METHOD

An experimental feature.

Accepted Values: $[0 ; 10]$

Default Value: 0

Groups: *Simplex optimizer*

MSK_IPAR_SIM_DUAL_RESTRICT_SELECTION

The dual simplex optimizer can use a so-called restricted selection/pricing strategy to choose the outgoing variable. Hence, if restricted selection is applied, then the dual simplex optimizer first choose a subset of all the potential outgoing variables. Next, for some time it will choose the outgoing variable only among the subset. From time to time the subset is redefined.

A larger value of this parameter implies that the optimizer will be more aggressive in its restriction strategy, i.e. a value of 0 implies that the restriction strategy is not applied at all.

Accepted Values: $[0 ; 100]$

Default Value: 50

Groups: *Dual simplex optimizer*

MSK_IPAR_SIM_DUAL_SELECTION

Controls the choice of the incoming variable, known as the selection strategy, in the dual simplex optimizer.

Accepted Values: *MSKsimseltypee*

Default Value: *MSK_SIM_SELECTION_FREE*

Groups: *Dual simplex optimizer*

MSK_IPAR_SIM_EXPLOIT_DUPVEC

Controls if the simplex optimizers are allowed to exploit duplicated columns.

Accepted Values: *MSKsimdupvece*

Default Value: *MSK_SIM_EXPLOIT_DUPVEC_OFF*

Groups: *Simplex optimizer*

MSK_IPAR_SIM_HOTSTART

Controls the type of hot-start that the simplex optimizer perform.

Accepted Values: *MSKsimhotstarte*

Default Value: *MSK_SIM_HOTSTART_FREE*

Groups: *Simplex optimizer*

MSK_IPAR_SIM_HOTSTART_LU

Determines if the simplex optimizer should exploit the initial factorization.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

MSK_IPAR_SIM_INTEGER

An experimental feature.

Accepted Values: [0 ;10]

Default Value: 0

Groups: *Simplex optimizer*

MSK_IPAR_SIM_MAX_ITERATIONS

Maximum number of iterations that can be used by a simplex optimizer.

Accepted Values: [0 ;+inf]

Default Value: 10000000

Groups: *Simplex optimizer, Termination criterion*

MSK_IPAR_SIM_MAX_NUM_SETBACKS

Controls how many set-backs are allowed within a simplex optimizer. A set-back is an event where the optimizer moves in the wrong direction. This is impossible in theory but may happen due to numerical problems.

Accepted Values: [0 ;+inf]

Default Value: 250

Groups: *Simplex optimizer*

MSK_IPAR_SIM_NON_SINGULAR

Controls if the simplex optimizer ensures a non-singular basis, if possible.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Simplex optimizer*

MSK_IPAR_SIM_PRIMAL_CRASH

Controls whether crashing is performed in the primal simplex optimizer.

In general, if a basis consists of more than (100-this parameter value)% fixed variables, then a crash will be performed.

Accepted Values: [0 ;+inf]

Default Value: 90

Groups: *Primal simplex optimizer*

MSK_IPAR_SIM_PRIMAL_PHASEONE_METHOD

An experimental feature.

Accepted Values: [0 ;10]

Default Value: 0

Groups: *Simplex optimizer*

MSK_IPAR_SIM_PRIMAL_RESTRICT_SELECTION

The primal simplex optimizer can use a so-called restricted selection/pricing strategy to choose the outgoing variable. Hence, if restricted selection is applied, then the primal simplex optimizer first choose a subset of all the potential incoming variables. Next, for some time it will choose the incoming variable only among the subset. From time to time the subset is redefined.

A larger value of this parameter implies that the optimizer will be more aggressive in its restriction strategy, i.e. a value of 0 implies that the restriction strategy is not applied at all.

Accepted Values: [0 ;100]

Default Value: 50

Groups: *Primal simplex optimizer*

MSK_IPAR_SIM_PRIMAL_SELECTION

Controls the choice of the incoming variable, known as the selection strategy, in the primal simplex optimizer.

Accepted Values: *MSKsimseltypee*

Default Value: *MSK_SIM_SELECTION_FREE*

Groups: *Primal simplex optimizer*

MSK_IPAR_SIM_REFACTOR_FREQ

Controls how frequent the basis is refactorized. The value 0 means that the optimizer determines the best point of refactorization.

It is strongly recommended NOT to change this parameter.

Accepted Values: *[0 ;+inf]*

Default Value: *0*

Groups: *Simplex optimizer*

MSK_IPAR_SIM_REFORMULATION

Controls if the simplex optimizers are allowed to reformulate the problem.

Accepted Values: *MSKsimreforme*

Default Value: *MSK_SIM_REFORMULATION_OFF*

Groups: *Simplex optimizer*

MSK_IPAR_SIM_SAVE_LU

Controls if the LU factorization stored should be replaced with the LU factorization corresponding to the initial basis.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Simplex optimizer*

MSK_IPAR_SIM_SCALING

Controls how much effort is used in scaling the problem before a simplex optimizer is used.

Accepted Values: *MSKscalingtypee*

Default Value: *MSK_SCALING_FREE*

Groups: *Simplex optimizer*

MSK_IPAR_SIM_SCALING_METHOD

Controls how the problem is scaled before a simplex optimizer is used.

Accepted Values: *MSKscalingmethode*

Default Value: *MSK_SCALING_METHOD_POW2*

Groups: *Simplex optimizer*

MSK_IPAR_SIM_SOLVE_FORM

Controls whether the primal or the dual problem is solved by the primal-/dual-simplex optimizer.

Accepted Values: *MSKsolveforme*

Default Value: *MSK_SOLVE_FREE*

Groups: *Simplex optimizer*

MSK_IPAR_SIM_STABILITY_PRIORITY

Controls how high priority the numerical stability should be given.

Accepted Values: *[0 ;100]*

Default Value: *50*

Groups: *Simplex optimizer*

MSK_IPAR_SIM_SWITCH_OPTIMIZER

The simplex optimizer sometimes chooses to solve the dual problem instead of the primal problem. This implies that if you have chosen to use the dual simplex optimizer and the problem is dualized, then it actually makes sense to use the primal simplex optimizer instead. If this parameter is on and the problem is dualized and furthermore the simplex optimizer is chosen to be the primal (dual) one, then it is switched to the dual (primal).

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Simplex optimizer*

MSK_IPAR_SOLUTION_CALLBACK

Indicates whether solution call-backs will be performed during the optimization.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Progress call-back, Overall solver*

MSK_IPAR_SOL_FILTER_KEEP_BASIC

If turned on, then basic and super basic constraints and variables are written to the solution file independent of the filter setting.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Solution input/output*

MSK_IPAR_SOL_FILTER_KEEP_RANGED

If turned on, then ranged constraints and variables are written to the solution file independent of the filter setting.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Solution input/output*

MSK_IPAR_SOL_READ_NAME_WIDTH

When a solution is read by **MOSEK** and some constraint, variable or cone names contain blanks, then a maximum name width must be specified. A negative value implies that no name contain blanks.

Accepted Values: *[-inf ;+inf]*

Default Value: *-1*

Groups: *Data input/output, Solution input/output*

MSK_IPAR_SOL_READ_WIDTH

Controls the maximal acceptable width of line in the solutions when read by **MOSEK**.

Accepted Values: *[0 ;+inf]*

Default Value: *1024*

Groups: *Data input/output, Solution input/output*

MSK_IPAR_TIMING_LEVEL

Controls the amount of timing performed inside **MOSEK**.

Accepted Values: *[0 ;+inf]*

Default Value: *1*

Groups: *Optimization system*

MSK_IPAR_WRITE_BAS_CONSTRAINTS

Controls whether the constraint section is written to the basic solution file.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output, Solution input/output*

MSK_IPAR_WRITE_BAS_HEAD

Controls whether the header section is written to the basic solution file.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output, Solution input/output*

MSK_IPAR_WRITE_BAS_VARIABLES

Controls whether the variables section is written to the basic solution file.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output, Solution input/output*

MSK_IPAR_WRITE_DATA_COMPRESSED

Controls whether the data file is compressed while it is written. 0 means no compression while higher values mean more compression.

Accepted Values: *[0 ;+inf]*

Default Value: *0*

Groups: *Data input/output*

MSK_IPAR_WRITE_DATA_FORMAT

Controls the file format when writing task data to a file.

Accepted Values: *MSKdataformate*

Default Value: *MSK_DATA_FORMAT_EXTENSION*

Groups: *Data input/output*

MSK_IPAR_WRITE_DATA_PARAM

If this option is turned on the parameter settings are written to the data file as parameters.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Data input/output*

MSK_IPAR_WRITE_FREE_CON

Controls whether the free constraints are written to the data file.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output*

MSK_IPAR_WRITE_GENERIC_NAMES

Controls whether the generic names or user-defined names are used in the data file.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Data input/output*

MSK_IPAR_WRITE_GENERIC_NAMES_IO

Index origin used in generic names.

Accepted Values: [0 ;+inf]

Default Value: 1

Groups: *Data input/output*

MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_ITEMS

Controls if the writer ignores incompatible problem items when writing files.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_OFF*

Groups: *Data input/output*

MSK_IPAR_WRITE_INT_CONSTRAINTS

Controls whether the constraint section is written to the integer solution file.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output, Solution input/output*

MSK_IPAR_WRITE_INT_HEAD

Controls whether the header section is written to the integer solution file.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output, Solution input/output*

MSK_IPAR_WRITE_INT_VARIABLES

Controls whether the variables section is written to the integer solution file.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output, Solution input/output*

MSK_IPAR_WRITE_LP_FULL_OBJ

Write all variables, including the ones with 0-coefficients, in the objective.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output*

MSK_IPAR_WRITE_LP_LINE_WIDTH

Maximum width of line in an LP file written by **MOSEK**.

Accepted Values: [40 ;+inf]

Default Value: 80

Groups: *Data input/output*

MSK_IPAR_WRITE_LP_QUOTED_NAMES

If this option is turned on, then **MOSEK** will quote invalid LP names when writing an LP file.

Accepted Values: *MSKonoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output*

MSK_IPAR_WRITE_LP_STRICT_FORMAT

Controls whether LP output files satisfy the LP format strictly.

Accepted Values: *MSKOnoffkeye*

Default Value: *MSK_OFF*

Groups: *Data input/output*

MSK_IPAR_WRITE_LP_TERMS_PER_LINE

Maximum number of terms on a single line in an LP file written by **MOSEK**. 0 means unlimited.

Accepted Values: *[0 ;+inf]*

Default Value: *10*

Groups: *Data input/output*

MSK_IPAR_WRITE_MPS_FORMAT

Controls in which format the MPS is written.

Accepted Values: *MSKmpsformate*

Default Value: *MSK_MPS_FORMAT_FREE*

Groups: *Data input/output*

MSK_IPAR_WRITE_MPS_INT

Controls if marker records are written to the MPS file to indicate whether variables are integer restricted.

Accepted Values: *MSKOnoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output*

MSK_IPAR_WRITE_PRECISION

Controls the precision with which double numbers are printed in the MPS data file. In general it is not worthwhile to use a value higher than 15.

Accepted Values: *[0 ;+inf]*

Default Value: *15*

Groups: *Data input/output*

MSK_IPAR_WRITE_SOL_BARVARIABLES

Controls whether the symmetric matrix variables section is written to the solution file.

Accepted Values: *MSKOnoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output, Solution input/output*

MSK_IPAR_WRITE_SOL_CONSTRAINTS

Controls whether the constraint section is written to the solution file.

Accepted Values: *MSKOnoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output, Solution input/output*

MSK_IPAR_WRITE_SOL_HEAD

Controls whether the header section is written to the solution file.

Accepted Values: *MSKOnoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output, Solution input/output*

MSK_IPAR_WRITE_SOL_IGNORE_INVALID_NAMES

Even if the names are invalid MPS names, then they are employed when writing the solution file.

Accepted Values: *MSK_onoffkeye*

Default Value: *MSK_OFF*

Groups: *Data input/output, Solution input/output*

MSK_IPAR_WRITE_SOL_VARIABLES

Controls whether the variables section is written to the solution file.

Accepted Values: *MSK_onoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output, Solution input/output*

MSK_IPAR_WRITE_TASK_INC_SOL

Controls whether the solutions are stored in the task file too.

Accepted Values: *MSK_onoffkeye*

Default Value: *MSK_ON*

Groups: *Data input/output*

MSK_IPAR_WRITE_XML_MODE

Controls if linear coefficients should be written by row or column when writing in the XML file format.

Accepted Values: *MSK_xmlwriteroutputtypee*

Default Value: *MSK_WRITE_XML_MODE_ROW*

Groups: *Data input/output*

String Parameters

MSK_SPAR_BAS_SOL_FILE_NAME

Name of the bas solution file.

Accepted Values: Any valid file name.

Groups: *Data input/output, Solution input/output*

MSK_SPAR_DATA_FILE_NAME

Data are read and written to this file.

Accepted Values: Any valid file name.

Groups: *Data input/output*

MSK_SPAR_DEBUG_FILE_NAME

MOSEK debug file.

Accepted Values: Any valid file name.

Groups: *Data input/output*

MSK_SPAR_INT_SOL_FILE_NAME

Name of the int solution file.

Accepted Values: Any valid file name.

Groups: *Data input/output, Solution input/output*

MSK_SPAR_ITR_SOL_FILE_NAME

Name of the itr solution file.

Accepted Values: Any valid file name.

- Groups: *Data input/output, Solution input/output*
- MSK_SPAR_MIO_DEBUG_STRING**
For internal use only.
- Accepted Values: Any valid string.
- Groups: *Data input/output*
- MSK_SPAR_PARAM_COMMENT_SIGN**
Only the first character in this string is used. It is considered as a start of comment sign in the **MOSEK** parameter file. Spaces are ignored in the string.
- Accepted Values: Any valid string.
- Default Value: %%
- Groups: *Data input/output*
- MSK_SPAR_PARAM_READ_FILE_NAME**
Modifications to the parameter database is read from this file.
- Accepted Values: Any valid file name.
- Groups: *Data input/output*
- MSK_SPAR_PARAM_WRITE_FILE_NAME**
The parameter database is written to this file.
- Accepted Values: Any valid file name.
- Groups: *Data input/output*
- MSK_SPAR_READ_MPS_BOU_NAME**
Name of the BOUNDS vector used. An empty name means that the first BOUNDS vector is used.
- Accepted Values: Any valid MPS name.
- Groups: *Data input/output*
- MSK_SPAR_READ_MPS_OBJ_NAME**
Name of the free constraint used as objective function. An empty name means that the first constraint is used as objective function.
- Accepted Values: Any valid MPS name.
- Groups: *Data input/output*
- MSK_SPAR_READ_MPS_RAN_NAME**
Name of the RANGE vector used. An empty name means that the first RANGE vector is used.
- Accepted Values: Any valid MPS name.
- Groups: *Data input/output*
- MSK_SPAR_READ_MPS_RHS_NAME**
Name of the RHS used. An empty name means that the first RHS vector is used.
- Accepted Values: Any valid MPS name.
- Groups: *Data input/output*
- MSK_SPAR_REMOTE_ACCESS_TOKEN**
An access token used to submit tasks to a remote **MOSEK** server. An access token is a random 32-byte string encoded in base64, i.e. it is a 44 character ASCII string.
- Accepted Values: Any valid string.
- MSK_SPAR_SENSITIVITY_FILE_NAME**
If defined, **MOSEK** reads this file as a sensitivity analysis data file specifying the type of analysis to be done.
- Accepted Values: Any valid string.

Groups: *Data input/output*

MSK_SPAR_SENSITIVITY_RES_FILE_NAME

Accepted Values: Any valid string.

Groups: *Data input/output*

MSK_SPAR_SOL_FILTER_XC_LOW

A filter used to determine which constraints should be listed in the solution file. A value of 0.5 means that all constraints having $xc[i] > 0.5$ should be listed, whereas +0.5 means that all constraints having $xc[i] \geq blc[i] + 0.5$ should be listed. An empty filter means that no filter is applied.

Accepted Values: Any valid filter.

Groups: *Data input/output, Solution input/output*

MSK_SPAR_SOL_FILTER_XC_UPR

A filter used to determine which constraints should be listed in the solution file. A value of 0.5 means that all constraints having $xc[i] < 0.5$ should be listed, whereas -0.5 means all constraints having $xc[i] \leq buc[i] - 0.5$ should be listed. An empty filter means that no filter is applied.

Accepted Values: Any valid filter.

Groups: *Data input/output, Solution input/output*

MSK_SPAR_SOL_FILTER_XX_LOW

A filter used to determine which variables should be listed in the solution file. A value of "0.5" means that all constraints having $xx[j] \geq 0.5$ should be listed, whereas "+0.5" means that all constraints having $xx[j] \geq blx[j] + 0.5$ should be listed. An empty filter means no filter is applied.

Accepted Values: Any valid filter.

Groups: *Data input/output, Solution input/output*

MSK_SPAR_SOL_FILTER_XX_UPR

A filter used to determine which variables should be listed in the solution file. A value of "0.5" means that all constraints having $xx[j] < 0.5$ should be printed, whereas "-0.5" means all constraints having $xx[j] \leq bux[j] - 0.5$ should be listed. An empty filter means no filter is applied.

Accepted Values: Any valid file name.

Groups: *Data input/output, Solution input/output*

MSK_SPAR_STAT_FILE_NAME

Statistics file name.

Accepted Values: Any valid file name.

Groups: *Data input/output*

MSK_SPAR_STAT_KEY

Key used when writing the summary file.

Accepted Values: Any valid XML string.

Groups: *Data input/output*

MSK_SPAR_STAT_NAME

Name used when writing the statistics file.

Accepted Values: Any valid XML string.

Groups: *Data input/output*

MSK_SPAR_WRITE_LP_GEN_VAR_NAME

Sometimes when an LP file is written additional variables must be inserted. They will have the prefix denoted by this parameter.

Accepted Values: Any valid string.

Default Value: xmskgen

Groups: *Data input/output*

9.2.2 Dual simplex optimizer parameters.

- *MSK_IPAR_SIM_DUAL_CRASH*
- *MSK_IPAR_SIM_DUAL_RESTRICT_SELECTION*
- *MSK_IPAR_SIM_DUAL_SELECTION*

9.2.3 Logging parameters.

- *MSK_IPAR_LOG*
- *MSK_IPAR_LOG_ANA_PRO*
- *MSK_IPAR_LOG_BI*
- *MSK_IPAR_LOG_BI_FREQ*
- *MSK_IPAR_LOG_CUT_SECOND_OPT*
- *MSK_IPAR_LOG_EXPAND*
- *MSK_IPAR_LOG_FACTOR*
- *MSK_IPAR_LOG_FEAS_REPAIR*
- *MSK_IPAR_LOG_FILE*
- *MSK_IPAR_LOG_HEAD*
- *MSK_IPAR_LOG_INFEAS_ANA*
- *MSK_IPAR_LOG_INTPNT*
- *MSK_IPAR_LOG_MIO*
- *MSK_IPAR_LOG_MIO_FREQ*
- *MSK_IPAR_LOG_OPTIMIZER*
- *MSK_IPAR_LOG_ORDER*
- *MSK_IPAR_LOG_PRESOLVE*
- *MSK_IPAR_LOG_RESPONSE*
- *MSK_IPAR_LOG_SENSITIVITY*
- *MSK_IPAR_LOG_SENSITIVITY_OPT*
- *MSK_IPAR_LOG_SIM*
- *MSK_IPAR_LOG_SIM_FREQ*
- *MSK_IPAR_LOG_STORAGE*

9.2.4 Analysis parameters.

- *MSK_IPAR_ANA_SOL_BASIS*
- *MSK_DPAR_ANA_SOL_INFEAS_TOL*
- *MSK_IPAR_ANA_SOL_PRINT_VIOLATED*
- *MSK_IPAR_LOG_ANA_PRO*

9.2.5 Basis identification parameters.

- *MSK_IPAR_BI_CLEAN_OPTIMIZER*
- *MSK_IPAR_BI_IGNORE_MAX_ITER*
- *MSK_IPAR_BI_IGNORE_NUM_ERROR*
- *MSK_IPAR_BI_MAX_ITERATIONS*
- *MSK_IPAR_INTPNT_BASIS*
- *MSK_IPAR_LOG_BI*
- *MSK_IPAR_LOG_BI_FREQ*
- *MSK_DPAR_SIM_LU_TOL_REL_PIV*

9.2.6 Overall solver parameters.

- *MSK_IPAR_BI_CLEAN_OPTIMIZER*
- *MSK_IPAR_INFEAS_PREFER_PRIMAL*
- *MSK_IPAR_LICENSE_WAIT*
- *MSK_IPAR_MIO_MODE*
- *MSK_IPAR_OPTIMIZER*
- *MSK_IPAR_PRESOLVE_LEVEL*
- *MSK_IPAR_PRESOLVE_USE*
- *MSK_IPAR_PRIMAL_REPAIR_OPTIMIZER*
- *MSK_IPAR_SENSITIVITY_ALL*
- *MSK_IPAR_SENSITIVITY_OPTIMIZER*
- *MSK_IPAR_SENSITIVITY_TYPE*
- *MSK_IPAR_SOLUTION_CALLBACK*

9.2.7 Data check parameters.

- *MSK_IPAR_CHECK_CONVEXITY*
- *MSK_DPAR_DATA_SYM_MAT_TOL*
- *MSK_DPAR_DATA_SYM_MAT_TOL_HUGE*
- *MSK_DPAR_DATA_SYM_MAT_TOL_LARGE*
- *MSK_DPAR_DATA_TOL_AIJ*
- *MSK_DPAR_DATA_TOL_AIJ_HUGE*
- *MSK_DPAR_DATA_TOL_AIJ_LARGE*
- *MSK_DPAR_DATA_TOL_BOUND_INF*
- *MSK_DPAR_DATA_TOL_BOUND_WRN*
- *MSK_DPAR_DATA_TOL_C_HUGE*
- *MSK_DPAR_DATA_TOL_CJ_LARGE*
- *MSK_DPAR_DATA_TOL_QIJ*
- *MSK_DPAR_DATA_TOL_X*

- *MSK_IPAR_LOG_CHECK_CONVEXITY*
- *MSK_DPAR_SEMIDEFINITE_TOL_APPROX*

9.2.8 Presolve parameters.

- *MSK_IPAR_PRESOLVE_ELIMINATOR_MAX_FILL*
- *MSK_IPAR_PRESOLVE_ELIMINATOR_MAX_NUM_TRIES*
- *MSK_IPAR_PRESOLVE_LEVEL*
- *MSK_IPAR_PRESOLVE_LINDEP_ABS_WORK_TRH*
- *MSK_IPAR_PRESOLVE_LINDEP_REL_WORK_TRH*
- *MSK_IPAR_PRESOLVE_LINDEP_USE*
- *MSK_DPAR_PRESOLVE_TOL_ABS_LINDEP*
- *MSK_DPAR_PRESOLVE_TOL_AIJ*
- *MSK_DPAR_PRESOLVE_TOL_REL_LINDEP*
- *MSK_DPAR_PRESOLVE_TOL_S*
- *MSK_DPAR_PRESOLVE_TOL_X*
- *MSK_IPAR_PRESOLVE_USE*

9.2.9 Termination criterion parameters.

- *MSK_DPAR_BASIS_REL_TOL_S*
- *MSK_DPAR_BASIS_TOL_S*
- *MSK_DPAR_BASIS_TOL_X*
- *MSK_IPAR_BI_MAX_ITERATIONS*
- *MSK_DPAR_INTPNT_CO_TOL_DFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_INFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_MU_RED*
- *MSK_DPAR_INTPNT_CO_TOL_NEAR_REL*
- *MSK_DPAR_INTPNT_CO_TOL_PFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_REL_GAP*
- *MSK_IPAR_INTPNT_MAX_ITERATIONS*
- *MSK_DPAR_INTPNT_NL_TOL_DFEAS*
- *MSK_DPAR_INTPNT_NL_TOL_MU_RED*
- *MSK_DPAR_INTPNT_NL_TOL_NEAR_REL*
- *MSK_DPAR_INTPNT_NL_TOL_PFEAS*
- *MSK_DPAR_INTPNT_NL_TOL_REL_GAP*
- *MSK_DPAR_INTPNT_QO_TOL_DFEAS*
- *MSK_DPAR_INTPNT_QO_TOL_INFEAS*
- *MSK_DPAR_INTPNT_QO_TOL_MU_RED*
- *MSK_DPAR_INTPNT_QO_TOL_NEAR_REL*

- *MSK_DPAR_INTPNT_QO_TOL_PFEAS*
- *MSK_DPAR_INTPNT_QO_TOL_REL_GAP*
- *MSK_DPAR_INTPNT_TOL_DFEAS*
- *MSK_DPAR_INTPNT_TOL_INFEAS*
- *MSK_DPAR_INTPNT_TOL_MU_RED*
- *MSK_DPAR_INTPNT_TOL_PFEAS*
- *MSK_DPAR_INTPNT_TOL_REL_GAP*
- *MSK_DPAR_LOWER_OBJ_CUT*
- *MSK_DPAR_LOWER_OBJ_CUT_FINITE_TRH*
- *MSK_DPAR_MIO_DISABLE_TERM_TIME*
- *MSK_IPAR_MIO_MAX_NUM_BRANCHES*
- *MSK_IPAR_MIO_MAX_NUM_SOLUTIONS*
- *MSK_DPAR_MIO_MAX_TIME*
- *MSK_DPAR_MIO_NEAR_TOL_REL_GAP*
- *MSK_DPAR_MIO_REL_GAP_CONST*
- *MSK_DPAR_MIO_TOL_REL_GAP*
- *MSK_DPAR_OPTIMIZER_MAX_TIME*
- *MSK_IPAR_SIM_MAX_ITERATIONS*
- *MSK_DPAR_UPPER_OBJ_CUT*
- *MSK_DPAR_UPPER_OBJ_CUT_FINITE_TRH*

9.2.10 Infeasibility report parameters.

- *MSK_IPAR_INFEAS_GENERIC_NAMES*
- *MSK_IPAR_INFEAS_REPORT_LEVEL*
- *MSK_IPAR_LOG_INFEAS_ANA*

9.2.11 Data input/output parameters.

- *MSK_SPAR_BAS_SOL_FILE_NAME*
- *MSK_SPAR_DATA_FILE_NAME*
- *MSK_SPAR_DEBUG_FILE_NAME*
- *MSK_IPAR_INFEAS_REPORT_AUTO*
- *MSK_SPAR_INT_SOL_FILE_NAME*
- *MSK_SPAR_ITR_SOL_FILE_NAME*
- *MSK_IPAR_LOG_FILE*
- *MSK_SPAR_MIO_DEBUG_STRING*
- *MSK_IPAR_OPF_MAX_TERMS_PER_LINE*
- *MSK_IPAR_OPF_WRITE_HEADER*
- *MSK_IPAR_OPF_WRITE_HINTS*

- *MSK_IPAR_OPF_WRITE_PARAMETERS*
- *MSK_IPAR_OPF_WRITE_PROBLEM*
- *MSK_IPAR_OPF_WRITE_SOL_BAS*
- *MSK_IPAR_OPF_WRITE_SOL_ITG*
- *MSK_IPAR_OPF_WRITE_SOL_ITR*
- *MSK_IPAR_OPF_WRITE_SOLUTIONS*
- *MSK_SPAR_PARAM_COMMENT_SIGN*
- *MSK_IPAR_PARAM_READ_CASE_NAME*
- *MSK_SPAR_PARAM_READ_FILE_NAME*
- *MSK_IPAR_PARAM_READ_IGN_ERROR*
- *MSK_SPAR_PARAM_WRITE_FILE_NAME*
- *MSK_IPAR_READ_DATA_COMPRESSED*
- *MSK_IPAR_READ_DATA_FORMAT*
- *MSK_IPAR_READ_DEBUG*
- *MSK_IPAR_READ_KEEP_FREE_CON*
- *MSK_IPAR_READ_LP_DROP_NEW_VARS_IN_BOU*
- *MSK_IPAR_READ_LP_QUOTED_NAMES*
- *MSK_SPAR_READ_MPS_BOU_NAME*
- *MSK_IPAR_READ_MPS_FORMAT*
- *MSK_SPAR_READ_MPS_OBJ_NAME*
- *MSK_SPAR_READ_MPS_RAN_NAME*
- *MSK_SPAR_READ_MPS_RHS_NAME*
- *MSK_IPAR_READ_MPS_WIDTH*
- *MSK_IPAR_READ_TASK_IGNORE_PARAM*
- *MSK_SPAR_SENSITIVITY_FILE_NAME*
- *MSK_SPAR_SENSITIVITY_RES_FILE_NAME*
- *MSK_SPAR_SOL_FILTER_XC_LOW*
- *MSK_SPAR_SOL_FILTER_XC_UPR*
- *MSK_SPAR_SOL_FILTER_XX_LOW*
- *MSK_SPAR_SOL_FILTER_XX_UPR*
- *MSK_IPAR_SOL_READ_NAME_WIDTH*
- *MSK_IPAR_SOL_READ_WIDTH*
- *MSK_SPAR_STAT_FILE_NAME*
- *MSK_SPAR_STAT_KEY*
- *MSK_SPAR_STAT_NAME*
- *MSK_IPAR_WRITE_BAS_CONSTRAINTS*
- *MSK_IPAR_WRITE_BAS_HEAD*
- *MSK_IPAR_WRITE_BAS_VARIABLES*
- *MSK_IPAR_WRITE_DATA_COMPRESSED*

- *MSK_IPAR_WRITE_DATA_FORMAT*
- *MSK_IPAR_WRITE_DATA_PARAM*
- *MSK_IPAR_WRITE_FREE_CON*
- *MSK_IPAR_WRITE_GENERIC_NAMES*
- *MSK_IPAR_WRITE_GENERIC_NAMES_IO*
- *MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_ITEMS*
- *MSK_IPAR_WRITE_INT_CONSTRAINTS*
- *MSK_IPAR_WRITE_INT_HEAD*
- *MSK_IPAR_WRITE_INT_VARIABLES*
- *MSK_IPAR_WRITE_LP_FULL_OBJ*
- *MSK_IPAR_WRITE_LP_GEN_VAR_NAME*
- *MSK_IPAR_WRITE_LP_LINE_WIDTH*
- *MSK_IPAR_WRITE_LP_QUOTED_NAMES*
- *MSK_IPAR_WRITE_LP_STRICT_FORMAT*
- *MSK_IPAR_WRITE_LP_TERMS_PER_LINE*
- *MSK_IPAR_WRITE_MPS_FORMAT*
- *MSK_IPAR_WRITE_MPS_INT*
- *MSK_IPAR_WRITE_PRECISION*
- *MSK_IPAR_WRITE_SOL_BARVARIABLES*
- *MSK_IPAR_WRITE_SOL_CONSTRAINTS*
- *MSK_IPAR_WRITE_SOL_HEAD*
- *MSK_IPAR_WRITE_SOL_IGNORE_INVALID_NAMES*
- *MSK_IPAR_WRITE_SOL_VARIABLES*
- *MSK_IPAR_WRITE_TASK_INC_SOL*
- *MSK_IPAR_WRITE_XML_MODE*

9.2.12 Interior-point method parameters.

- *MSK_IPAR_BI_IGNORE_MAX_ITER*
- *MSK_IPAR_BI_IGNORE_NUM_ERROR*
- *MSK_DPAR_CHECK_CONVEXITY_REL_TOL*
- *MSK_IPAR_INTPNT_BASIS*
- *MSK_DPAR_INTPNT_CO_TOL_DFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_INFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_MU_RED*
- *MSK_DPAR_INTPNT_CO_TOL_NEAR_REL*
- *MSK_DPAR_INTPNT_CO_TOL_PFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_REL_GAP*
- *MSK_IPAR_INTPNT_DIFF_STEP*
- *MSK_IPAR_INTPNT_HOTSTART*

- *MSK_IPAR_INTPNT_MAX_ITERATIONS*
- *MSK_IPAR_INTPNT_MAX_NUM_COR*
- *MSK_IPAR_INTPNT_MAX_NUM_REFINEMENT_STEPS*
- *MSK_DPAR_INTPNT_NL_MERIT_BAL*
- *MSK_DPAR_INTPNT_NL_TOL_DFEAS*
- *MSK_DPAR_INTPNT_NL_TOL_MU_RED*
- *MSK_DPAR_INTPNT_NL_TOL_NEAR_REL*
- *MSK_DPAR_INTPNT_NL_TOL_PFEAS*
- *MSK_DPAR_INTPNT_NL_TOL_REL_GAP*
- *MSK_DPAR_INTPNT_NL_TOL_REL_STEP*
- *MSK_IPAR_INTPNT_OFF_COL_TRH*
- *MSK_IPAR_INTPNT_ORDER_METHOD*
- *MSK_DPAR_INTPNT_QO_TOL_DFEAS*
- *MSK_DPAR_INTPNT_QO_TOL_INFEAS*
- *MSK_DPAR_INTPNT_QO_TOL_MU_RED*
- *MSK_DPAR_INTPNT_QO_TOL_NEAR_REL*
- *MSK_DPAR_INTPNT_QO_TOL_PFEAS*
- *MSK_DPAR_INTPNT_QO_TOL_REL_GAP*
- *MSK_IPAR_INTPNT_REGULARIZATION_USE*
- *MSK_IPAR_INTPNT_SCALING*
- *MSK_IPAR_INTPNT_SOLVE_FORM*
- *MSK_IPAR_INTPNT_STARTING_POINT*
- *MSK_DPAR_INTPNT_TOL_DFEAS*
- *MSK_DPAR_INTPNT_TOL_DSAFE*
- *MSK_DPAR_INTPNT_TOL_INFEAS*
- *MSK_DPAR_INTPNT_TOL_MU_RED*
- *MSK_DPAR_INTPNT_TOL_PATH*
- *MSK_DPAR_INTPNT_TOL_PFEAS*
- *MSK_DPAR_INTPNT_TOL_PSAFE*
- *MSK_DPAR_INTPNT_TOL_REL_GAP*
- *MSK_DPAR_INTPNT_TOL_REL_STEP*
- *MSK_DPAR_INTPNT_TOL_STEP_SIZE*
- *MSK_IPAR_LOG_INTPNT*
- *MSK_IPAR_LOG_PRESOLVE*
- *MSK_DPAR_QCQO_REFORMULATE_REL_DROP_TOL*

9.2.13 Debugging parameters.

- *MSK_IPAR_AUTO_SORT_A_BEFORE_OPT*

9.2.14 Solution input/output parameters.

- *MSK_SPAR_BAS_SOL_FILE_NAME*
- *MSK_IPAR_INFEAS_REPORT_AUTO*
- *MSK_SPAR_INT_SOL_FILE_NAME*
- *MSK_SPAR_ITR_SOL_FILE_NAME*
- *MSK_IPAR_SOL_FILTER_KEEP_BASIC*
- *MSK_IPAR_SOL_FILTER_KEEP_RANGED*
- *MSK_SPAR_SOL_FILTER_XC_LOW*
- *MSK_SPAR_SOL_FILTER_XC_UPR*
- *MSK_SPAR_SOL_FILTER_XX_LOW*
- *MSK_SPAR_SOL_FILTER_XX_UPR*
- *MSK_IPAR_SOL_READ_NAME_WIDTH*
- *MSK_IPAR_SOL_READ_WIDTH*
- *MSK_IPAR_WRITE_BAS_CONSTRAINTS*
- *MSK_IPAR_WRITE_BAS_HEAD*
- *MSK_IPAR_WRITE_BAS_VARIABLES*
- *MSK_IPAR_WRITE_INT_CONSTRAINTS*
- *MSK_IPAR_WRITE_INT_HEAD*
- *MSK_IPAR_WRITE_INT_VARIABLES*
- *MSK_IPAR_WRITE_SOL_BARVARIABLES*
- *MSK_IPAR_WRITE_SOL_CONSTRAINTS*
- *MSK_IPAR_WRITE_SOL_HEAD*
- *MSK_IPAR_WRITE_SOL_IGNORE_INVALID_NAMES*
- *MSK_IPAR_WRITE_SOL_VARIABLES*

9.2.15 Progress call-back parameters.

- *MSK_IPAR_SOLUTION_CALLBACK*

9.2.16 Conic interior-point method parameters.

- *MSK_DPAR_INTPNT_CO_TOL_DFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_INFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_MU_RED*
- *MSK_DPAR_INTPNT_CO_TOL_NEAR_REL*
- *MSK_DPAR_INTPNT_CO_TOL_PFEAS*
- *MSK_DPAR_INTPNT_CO_TOL_REL_GAP*

9.2.17 Simplex optimizer parameters.

- *MSK_DPAR_BASIS_REL_TOL_S*
- *MSK_IPAR_BASIS_SOLVE_USE_PLUS_ONE*
- *MSK_DPAR_BASIS_TOL_S*
- *MSK_DPAR_BASIS_TOL_X*
- *MSK_IPAR_LOG_SIM*
- *MSK_IPAR_LOG_SIM_FREQ*
- *MSK_IPAR_LOG_SIM_MINOR*
- *MSK_IPAR_SENSITIVITY_OPTIMIZER*
- *MSK_IPAR_SIM_BASIS_FACTOR_USE*
- *MSK_IPAR_SIM_DEGEN*
- *MSK_IPAR_SIM_DUAL_PHASEONE_METHOD*
- *MSK_IPAR_SIM_EXPLOIT_DUPVEC*
- *MSK_IPAR_SIM_HOTSTART*
- *MSK_IPAR_SIM_INTEGER*
- *MSK_DPAR_SIM_LU_TOL_REL_PIV*
- *MSK_IPAR_SIM_MAX_ITERATIONS*
- *MSK_IPAR_SIM_MAX_NUM_SETBACKS*
- *MSK_IPAR_SIM_NON_SINGULAR*
- *MSK_IPAR_SIM_PRIMAL_PHASEONE_METHOD*
- *MSK_IPAR_SIM_REFACTOR_FREQ*
- *MSK_IPAR_SIM_REFORMULATION*
- *MSK_IPAR_SIM_SAVE_LU*
- *MSK_IPAR_SIM_SCALING*
- *MSK_IPAR_SIM_SCALING_METHOD*
- *MSK_IPAR_SIM_SOLVE_FORM*
- *MSK_IPAR_SIM_STABILITY_PRIORITY*
- *MSK_IPAR_SIM_SWITCH_OPTIMIZER*
- *MSK_DPAR_SIMPLEX_ABS_TOL_PIV*

9.2.18 Primal simplex optimizer parameters.

- *MSK_IPAR_SIM_PRIMAL_CRASH*
- *MSK_IPAR_SIM_PRIMAL_RESTRICT_SELECTION*
- *MSK_IPAR_SIM_PRIMAL_SELECTION*

9.2.19 Mixed-integer optimization parameters.

- *MSK_IPAR_LOG_MIO*
- *MSK_IPAR_LOG_MIO_FREQ*
- *MSK_IPAR_MIO_BRANCH_DIR*
- *MSK_IPAR_MIO_CONSTRUCT_SOL*
- *MSK_IPAR_MIO_CUT_CLIQUE*
- *MSK_IPAR_MIO_CUT_CMIR*
- *MSK_IPAR_MIO_CUT_GMI*
- *MSK_IPAR_MIO_CUT_IMPLIED_BOUND*
- *MSK_IPAR_MIO_CUT_KNAPSACK_COVER*
- *MSK_IPAR_MIO_CUT_SELECTION_LEVEL*
- *MSK_DPAR_MIO_DISABLE_TERM_TIME*
- *MSK_IPAR_MIO_HEURISTIC_LEVEL*
- *MSK_IPAR_MIO_MAX_NUM_BRANCHES*
- *MSK_IPAR_MIO_MAX_NUM_RELAXS*
- *MSK_IPAR_MIO_MAX_NUM_SOLUTIONS*
- *MSK_DPAR_MIO_MAX_TIME*
- *MSK_DPAR_MIO_NEAR_TOL_ABS_GAP*
- *MSK_DPAR_MIO_NEAR_TOL_REL_GAP*
- *MSK_IPAR_MIO_NODE_OPTIMIZER*
- *MSK_IPAR_MIO_NODE_SELECTION*
- *MSK_IPAR_MIO_PERSPECTIVE_REFORMULATE*
- *MSK_IPAR_MIO_PROBING_LEVEL*
- *MSK_DPAR_MIO_REL_GAP_CONST*
- *MSK_IPAR_MIO_RINS_MAX_NODES*
- *MSK_IPAR_MIO_ROOT_OPTIMIZER*
- *MSK_IPAR_MIO_ROOT_REPEAT_PREOLVE_LEVEL*
- *MSK_DPAR_MIO_TOL_ABS_GAP*
- *MSK_DPAR_MIO_TOL_ABS_RELAX_INT*
- *MSK_DPAR_MIO_TOL_FEAS*
- *MSK_DPAR_MIO_TOL_REL_DUAL_BOUND_IMPROVEMENT*
- *MSK_DPAR_MIO_TOL_REL_GAP*
- *MSK_IPAR_MIO_VB_DETECTION_LEVEL*

9.2.20 Optimization system parameters.

- *MSK_IPAR_AUTO_UPDATE_SOL_INFO*
- *MSK_IPAR_INTPNT_MULTI_THREAD*
- *MSK_IPAR_LICENSE_WAIT*

- *MSK_IPAR_LOG_STORAGE*
- *MSK_IPAR_MIO_MT_USER_CB*
- *MSK_IPAR_MT_SPINCOUNT*
- *MSK_IPAR_NUM_THREADS*
- *MSK_IPAR_TIMING_LEVEL*

9.2.21 License manager parameters.

- *MSK_IPAR_CACHE_LICENSE*
- *MSK_IPAR_LICENSE_DEBUG*
- *MSK_IPAR_LICENSE_PAUSE_TIME*
- *MSK_IPAR_LICENSE_SUPPRESS_EXPIRE_WRNS*
- *MSK_IPAR_LICENSE_WAIT*

9.2.22 Output information parameters.

- *MSK_IPAR_INFEAS_REPORT_LEVEL*
- *MSK_IPAR_LICENSE_SUPPRESS_EXPIRE_WRNS*
- *MSK_IPAR_LOG*
- *MSK_IPAR_LOG_BI*
- *MSK_IPAR_LOG_BI_FREQ*
- *MSK_IPAR_LOG_CUT_SECOND_OPT*
- *MSK_IPAR_LOG_EXPAND*
- *MSK_IPAR_LOG_FACTOR*
- *MSK_IPAR_LOG_FEAS_REPAIR*
- *MSK_IPAR_LOG_FILE*
- *MSK_IPAR_LOG_HEAD*
- *MSK_IPAR_LOG_INFEAS_ANA*
- *MSK_IPAR_LOG_INTPNT*
- *MSK_IPAR_LOG_MIO*
- *MSK_IPAR_LOG_MIO_FREQ*
- *MSK_IPAR_LOG_OPTIMIZER*
- *MSK_IPAR_LOG_ORDER*
- *MSK_IPAR_LOG_RESPONSE*
- *MSK_IPAR_LOG_SENSITIVITY*
- *MSK_IPAR_LOG_SENSITIVITY_OPT*
- *MSK_IPAR_LOG_SIM*
- *MSK_IPAR_LOG_SIM_FREQ*
- *MSK_IPAR_LOG_SIM_MINOR*
- *MSK_IPAR_LOG_STORAGE*

- *MSK_IPAR_MAX_NUM_WARNINGS*

9.2.23 Nonlinear convex method parameters.

- *MSK_IPAR_CHECK_CONVEXITY*
- *MSK_DPAR_INTPNT_NL_MERIT_BAL*
- *MSK_DPAR_INTPNT_NL_TOL_DFEAS*
- *MSK_DPAR_INTPNT_NL_TOL_MU_RED*
- *MSK_DPAR_INTPNT_NL_TOL_NEAR_REL*
- *MSK_DPAR_INTPNT_NL_TOL_PFEAS*
- *MSK_DPAR_INTPNT_NL_TOL_REL_GAP*
- *MSK_DPAR_INTPNT_NL_TOL_REL_STEP*
- *MSK_DPAR_INTPNT_TOL_INFEAS*
- *MSK_IPAR_LOG_CHECK_CONVEXITY*

9.3 Response codes

- *Termination codes*
- *Error codes*
- *Warning codes*

9.3.1 Termination Codes

MSK_RES_OK (0)

No error occurred.

MSK_RES_TRM_INTERNAL (10030)

The optimizer terminated due to some internal reason. Please contact **MOSEK** support.

MSK_RES_TRM_INTERNAL_STOP (10031)

The optimizer terminated for internal reasons. Please contact **MOSEK** support.

MSK_RES_TRM_MAX_ITERATIONS (10000)

The optimizer terminated at the maximum number of iterations.

MSK_RES_TRM_MAX_NUM_SETBACKS (10020)

The optimizer terminated as the maximum number of set-backs was reached. This indicates % serious numerical problems and a possibly badly formulated problem.

MSK_RES_TRM_MAX_TIME (10001)

The optimizer terminated at the maximum amount of time.

MSK_RES_TRM_MIO_NEAR_ABS_GAP (10004)

The mixed-integer optimizer terminated because the near optimal absolute gap tolerance was satisfied.

MSK_RES_TRM_MIO_NEAR_REL_GAP (10003)

The mixed-integer optimizer terminated because the near optimal relative gap tolerance was satisfied.

MSK_RES_TRM_MIO_NUM_BRANCHES (10009)

The mixed-integer optimizer terminated as to the maximum number of branches was reached.

MSK_RES_TRM_MIO_NUM_RELAXS (10008)

The mixed-integer optimizer terminated as the maximum number of relaxations was reached.

MSK_RES_TRM_NUM_MAX_NUM_INT_SOLUTIONS (10015)

The mixed-integer optimizer terminated as the maximum number of feasible solutions was reached.

MSK_RES_TRM_NUMERICAL_PROBLEM (10025)

The optimizer terminated due to numerical problems.

MSK_RES_TRM_OBJECTIVE_RANGE (10002)

The optimizer terminated on the bound of the objective range.

MSK_RES_TRM_STALL (10006)

The optimizer is terminated due to slow progress.

Stalling means that numerical problems prevent the optimizer from making reasonable progress and that it make no sense to continue. In many cases this happens if the problem is badly scaled or otherwise ill-conditioned. There is no guarantee that the solution will be (near) feasible or near optimal. However, often stalling happens near the optimum, and the returned solution may be of good quality. Therefore, it is recommended to check the status of then solution. If the solution near optimal the solution is most likely good enough for most practical purposes.

Please note that if a linear optimization problem is solved using the interior-point optimizer with basis identification turned on, the returned basic solution likely to have high accuracy, even though the optimizer stalled.

Some common causes of stalling are a) badly scaled models, b) near feasible or near infeasible problems and c) a non-convex problems. Case c) is only relevant for general non-linear problems. It is not possible in general for **MOSEK** to check if a specific problems is convex since such a check would be NP hard in itself. This implies that care should be taken when solving problems involving general user defined functions.

MSK_RES_TRM_USER_CALLBACK (10007)

The optimizer terminated due to the return of the user-defined call-back function.

9.3.2 Error Codes

MSK_RES_ERR_AD_INVALID_CODELIST (3102)

The code list data was invalid.

MSK_RES_ERR_API_ARRAY_TOO_SMALL (3001)

An input array was too short.

MSK_RES_ERR_API_CB_CONNECT (3002)

Failed to connect a callback object.

MSK_RES_ERR_API_FATAL_ERROR (3005)

An internal error occurred in the API. Please report this problem.

MSK_RES_ERR_API_INTERNAL (3999)

An internal fatal error occurred in an interface function.

MSK_RES_ERR_ARG_IS_TOO_LARGE (1227)

The value of a argument is too small.

MSK_RES_ERR_ARG_IS_TOO_SMALL (1226)

The value of a argument is too small.

MSK_RES_ERR_ARGUMENT_DIMENSION (1201)

A function argument is of incorrect dimension.

MSK_RES_ERR_ARGUMENT_IS_TOO_LARGE (5005)

The value of a function argument is too large.

MSK_RES_ERR_ARGUMENT_LENNEQ (1197)

Incorrect length of arguments.

MSK_RES_ERR_ARGUMENT_PERM_ARRAY (1299)

An invalid permutation array is specified.

MSK_RES_ERR_ARGUMENT_TYPE (1198)

Incorrect argument type.

MSK_RES_ERR_BAR_VAR_DIM (3920)

The dimension of a symmetric matrix variable has to be greater than 0.

MSK_RES_ERR_BASIS (1266)

An invalid basis is specified. Either too many or too few basis variables are specified.

MSK_RES_ERR_BASIS_FACTOR (1610)

The factorization of the basis is invalid.

MSK_RES_ERR_BASIS_SINGULAR (1615)

The basis is singular and hence cannot be factored.

MSK_RES_ERR_BLANK_NAME (1070)

An all blank name has been specified.

MSK_RES_ERR_CANNOT_CLONE_NL (2505)

A task with a nonlinear function call-back cannot be cloned.

MSK_RES_ERR_CANNOT_HANDLE_NL (2506)

A function cannot handle a task with nonlinear function call-backs.

MSK_RES_ERR_CBF_DUPLICATE_ACOORD (7116)

Duplicate index in ACOORD.

MSK_RES_ERR_CBF_DUPLICATE_BCOORD (7115)

Duplicate index in BCOORD.

MSK_RES_ERR_CBF_DUPLICATE_CON (7108)

Duplicate CON keyword.

MSK_RES_ERR_CBF_DUPLICATE_INT (7110)

Duplicate INT keyword.

MSK_RES_ERR_CBF_DUPLICATE_OBJ (7107)

Duplicate OBJ keyword.

MSK_RES_ERR_CBF_DUPLICATE_OBJCOORD (7114)

Duplicate index in OBJCOORD.

MSK_RES_ERR_CBF_DUPLICATE_VAR (7109)

Duplicate VAR keyword.

MSK_RES_ERR_CBF_INVALID_CON_TYPE (7112)

Invalid constraint type.

MSK_RES_ERR_CBF_INVALID_DOMAIN_DIMENSION (7113)

Invalid domain dimension.

MSK_RES_ERR_CBF_INVALID_INT_INDEX (7121)

Invalid INT index.

MSK_RES_ERR_CBF_INVALID_VAR_TYPE (7111)

Invalid variable type.

MSK_RES_ERR_CBF_NO_VARIABLES (7102)

No variables are specified.

MSK_RES_ERR_CBF_NO_VERSION_SPECIFIED (7105)

No version specified.

MSK_RES_ERR_CBF_OBJ_SENSE (7101)

An invalid objective sense is specified.

MSK_RES_ERR_CBF_PARSE (7100)

An error occurred while parsing an CBF file.

MSK_RES_ERR_CBF_SYNTAX (7106)

Invalid syntax.

MSK_RES_ERR_CBF_TOO_FEW_CONSTRAINTS (7118)

Too few constraints defined.

MSK_RES_ERR_CBF_TOO_FEW_INTS (7119)

Too few ints are specified.

MSK_RES_ERR_CBF_TOO_FEW_VARIABLES (7117)

Too few variables defined.

MSK_RES_ERR_CBF_TOO_MANY_CONSTRAINTS (7103)

Too many constraints specified.

MSK_RES_ERR_CBF_TOO_MANY_INTS (7120)

Too many ints are specified.

MSK_RES_ERR_CBF_TOO_MANY_VARIABLES (7104)

Too many variables specified.

MSK_RES_ERR_CBF_UNSUPPORTED (7122)

Unsupported feature is present.

MSK_RES_ERR_CON_Q_NOT_NSD (1294)

The quadratic constraint matrix is not negative semidefinite as expected for a constraint with finite lower bound. This results in a nonconvex problem. The parameter *MSK_DPAR_CHECK_CONVEXITY_REL_TOL* can be used to relax the convexity check.

MSK_RES_ERR_CON_Q_NOT_PSD (1293)

The quadratic constraint matrix is not positive semidefinite as expected for a constraint with finite upper bound. This results in a nonconvex problem. The parameter *MSK_DPAR_CHECK_CONVEXITY_REL_TOL* can be used to relax the convexity check.

MSK_RES_ERR_CONE_INDEX (1300)

An index of a non-existing cone has been specified.

MSK_RES_ERR_CONE_OVERLAP (1302)

One or more of the variables in the cone to be added is already member of another cone. Now assume the variable is x_j then add a new variable say x_k and the constraint

$$x_j = x_k$$

and then let x_k be member of the cone to be appended.

MSK_RES_ERR_CONE_OVERLAP_APPEND (1307)

The cone to be appended has one variable which is already member of another cone.

MSK_RES_ERR_CONE_REP_VAR (1303)

A variable is included multiple times in the cone.

MSK_RES_ERR_CONE_SIZE (1301)

A cone with too few members is specified.

MSK_RES_ERR_CONE_TYPE (1305)

Invalid cone type specified.

MSK_RES_ERR_CONE_TYPE_STR (1306)

Invalid cone type specified.

MSK_RES_ERR_DATA_FILE_EXT (1055)

The data file format cannot be determined from the file name.

MSK_RES_ERR_DUP_NAME (1071)

The same name was used multiple times for the same problem item type.

MSK_RES_ERR_DUPLICATE_AIJ (1385)

An element in the A matrix is specified twice.

MSK_RES_ERR_DUPLICATE_BARVARIABLE_NAMES (4502)

Two barvariable names are identical.

MSK_RES_ERR_DUPLICATE_CONE_NAMES (4503)

Two cone names are identical.

MSK_RES_ERR_DUPLICATE_CONSTRAINT_NAMES (4500)

Two constraint names are identical.

MSK_RES_ERR_DUPLICATE_VARIABLE_NAMES (4501)

Two variable names are identical.

MSK_RES_ERR_END_OF_FILE (1059)

End of file reached.

MSK_RES_ERR_FACTOR (1650)

An error occurred while factorizing a matrix.

MSK_RES_ERR_FEASREPAIR_CANNOT_RELAX (1700)

An optimization problem cannot be relaxed. This is the case e.g. for general nonlinear optimization problems.

MSK_RES_ERR_FEASREPAIR_INCONSISTENT_BOUND (1702)

The upper bound is less than the lower bound for a variable or a constraint. Please correct this before running the feasibility repair.

MSK_RES_ERR_FEASREPAIR_SOLVING_RELAXED (1701)

The relaxed problem could not be solved to optimality. Please consult the log file for further details.

MSK_RES_ERR_FILE_LICENSE (1007)

Invalid license file.

MSK_RES_ERR_FILE_OPEN (1052)

Error while opening a file.

MSK_RES_ERR_FILE_READ (1053)

File read error.

MSK_RES_ERR_FILE_WRITE (1054)

File write error.

MSK_RES_ERR_FIRST (1261)

Invalid first.

MSK_RES_ERR_FIRSTI (1285)

Invalid firsti.

MSK_RES_ERR_FIRSTJ (1287)

Invalid firstj.

MSK_RES_ERR_FIXED_BOUND_VALUES (1425)

A fixed constraint/variable has been specified using the bound keys but the numerical value of the lower and upper bound is different.

MSK_RES_ERR_FLEXLM (1014)

The FLEXlm license manager reported an error.

MSK_RES_ERR_GLOBAL_INV_CONIC_PROBLEM (1503)

The global optimizer can only be applied to problems without semidefinite variables.

MSK_RES_ERR_HUGE_AIJ (1380)

A numerically huge value is specified for an $a_{i,j}$ element in A. The parameter `MSK_DPAR_DATA_TOL_AIJ_HUGE` controls when an $a_{i,j}$ is considered huge.

MSK_RES_ERR_HUGE_C (1375)

A huge value in absolute size is specified for one c_j .

MSK_RES_ERR_IDENTICAL_TASKS (3101)

Some tasks related to this function call were identical. Unique tasks were expected.

MSK_RES_ERR_IN_ARGUMENT (1200)

A function argument is incorrect.

MSK_RES_ERR_INDEX (1235)

An index is out of range.

MSK_RES_ERR_INDEX_ARR_IS_TOO_LARGE (1222)

An index in an array argument is too large.

MSK_RES_ERR_INDEX_ARR_IS_TOO_SMALL (1221)

An index in an array argument is too small.

MSK_RES_ERR_INDEX_IS_TOO_LARGE (1204)

An index in an argument is too large.

MSK_RES_ERR_INDEX_IS_TOO_SMALL (1203)

An index in an argument is too small.

MSK_RES_ERR_INF_DOU_INDEX (1219)

A double information index is out of range for the specified type.

MSK_RES_ERR_INF_DOU_NAME (1230)

A double information name is invalid.

MSK_RES_ERR_INF_INT_INDEX (1220)

An integer information index is out of range for the specified type.

MSK_RES_ERR_INF_INT_NAME (1231)

An integer information name is invalid.

MSK_RES_ERR_INF_LINT_INDEX (1225)

A long integer information index is out of range for the specified type.

MSK_RES_ERR_INF_LINT_NAME (1234)

A long integer information name is invalid.

MSK_RES_ERR_INF_TYPE (1232)

The information type is invalid.

MSK_RES_ERR_INFEAS_UNDEFINED (3910)

The requested value is not defined for this solution type.

MSK_RES_ERR_INFINITE_BOUND (1400)

A numerically huge bound value is specified.

MSK_RES_ERR_INT64_TO_INT32_CAST (3800)

An 32 bit integer could not cast to a 64 bit integer.

MSK_RES_ERR_INTERNAL (3000)

An internal error occurred. Please report this problem.

MSK_RES_ERR_INTERNAL_TEST_FAILED (3500)

An internal unit test function failed.

MSK_RES_ERR_INV_APTRE (1253)

`aptre[j]` is strictly smaller than `aptrb[j]` for some `j`.

MSK_RES_ERR_INV_BK (1255)

Invalid bound key.

MSK_RES_ERR_INV_BKC (1256)

Invalid bound key is specified for a constraint.

MSK_RES_ERR_INV_BKX (1257)

An invalid bound key is specified for a variable.

MSK_RES_ERR_INV_CONE_TYPE (1272)
Invalid cone type code is encountered.

MSK_RES_ERR_INV_CONE_TYPE_STR (1271)
Invalid cone type string encountered.

MSK_RES_ERR_INV_MARKI (2501)
Invalid value in marki.

MSK_RES_ERR_INV_MARKJ (2502)
Invalid value in markj.

MSK_RES_ERR_INV_NAME_ITEM (1280)
An invalid name item code is used.

MSK_RES_ERR_INV_NUMI (2503)
Invalid numi.

MSK_RES_ERR_INV_NUMJ (2504)
Invalid numj.

MSK_RES_ERR_INV_OPTIMIZER (1550)
An invalid optimizer has been chosen for the problem. This means that the simplex or the conic optimizer is chosen to optimize a nonlinear problem.

MSK_RES_ERR_INV_PROBLEM (1500)
Invalid problem type. Probably a nonconvex problem has been specified.

MSK_RES_ERR_INV_QCON_SUBI (1405)
Invalid value in qcsubi.

MSK_RES_ERR_INV_QCON_SUBJ (1406)
Invalid value in qcsubj.

MSK_RES_ERR_INV_QCON_SUBK (1404)
Invalid value in qcsubk.

MSK_RES_ERR_INV_QCON_VAL (1407)
Invalid value in qcval.

MSK_RES_ERR_INV_QOBJ_SUBI (1401)
Invalid value in qosubi.

MSK_RES_ERR_INV_QOBJ_SUBJ (1402)
Invalid value in qosubj.

MSK_RES_ERR_INV_QOBJ_VAL (1403)
Invalid value in qoval.

MSK_RES_ERR_INV_SK (1270)
Invalid status key code.

MSK_RES_ERR_INV_SK_STR (1269)
Invalid status key string encountered.

MSK_RES_ERR_INV_SKC (1267)
Invalid value in skc.

MSK_RES_ERR_INV_SKN (1274)
Invalid value in skn.

MSK_RES_ERR_INV_SKX (1268)
Invalid value in skx.

MSK_RES_ERR_INV_VAR_TYPE (1258)
An invalid variable type is specified for a variable.

MSK_RES_ERR_INVALID_ACCMODE (2520)
An invalid access mode is specified.

MSK_RES_ERR_INVALID_AIJ (1473)

$a_{i,j}$ contains an invalid floating point value, i.e. a NaN or an infinite value.

MSK_RES_ERR_INVALID_AMPL_STUB (3700)

Invalid AMPL stub.

MSK_RES_ERR_INVALID_BARVAR_NAME (1079)

An invalid symmetric matrix variable name is used.

MSK_RES_ERR_INVALID_COMPRESSION (1800)

Invalid compression type.

MSK_RES_ERR_INVALID_CON_NAME (1076)

An invalid constraint name is used.

MSK_RES_ERR_INVALID_CONE_NAME (1078)

An invalid cone name is used.

MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_CONES (4005)

The file format does not support a problem with conic constraints.

MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_GENERAL_NL (4010)

The file format does not support a problem with general nonlinear terms.

MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_SYM_MAT (4000)

The file format does not support a problem with symmetric matrix variables.

MSK_RES_ERR_INVALID_FILE_NAME (1056)

An invalid file name has been specified.

MSK_RES_ERR_INVALID_FORMAT_TYPE (1283)

Invalid format type.

MSK_RES_ERR_INVALID_IDX (1246)

A specified index is invalid.

MSK_RES_ERR_INVALID_IOMODE (1801)

Invalid io mode.

MSK_RES_ERR_INVALID_MAX_NUM (1247)

A specified index is invalid.

MSK_RES_ERR_INVALID_NAME_IN_SOL_FILE (1170)

An invalid name occurred in a solution file.

MSK_RES_ERR_INVALID_OBJ_NAME (1075)

An invalid objective name is specified.

MSK_RES_ERR_INVALID_OBJECTIVE_SENSE (1445)

An invalid objective sense is specified.

MSK_RES_ERR_INVALID_PROBLEM_TYPE (6000)

An invalid problem type.

MSK_RES_ERR_INVALID_SOL_FILE_NAME (1057)

An invalid file name has been specified.

MSK_RES_ERR_INVALID_STREAM (1062)

An invalid stream is referenced.

MSK_RES_ERR_INVALID_SURPLUS (1275)

Invalid surplus.

MSK_RES_ERR_INVALID_SYM_MAT_DIM (3950)

A sparse symmetric matrix of invalid dimension is specified.

MSK_RES_ERR_INVALID_TASK (1064)

The `task` is invalid.

MSK_RES_ERR_INVALID_UTF8 (2900)
An invalid UTF8 string is encountered.

MSK_RES_ERR_INVALID_VAR_NAME (1077)
An invalid variable name is used.

MSK_RES_ERR_INVALID_WCHAR (2901)
An invalid `wchar` string is encountered.

MSK_RES_ERR_INVALID_WHICHSQL (1228)
`whichsol` is invalid.

MSK_RES_ERR_JSON_DATA (1179)
Inconsistent data in JSON Task file

MSK_RES_ERR_JSON_FORMAT (1178)
Error in an JSON Task file

MSK_RES_ERR_JSON_MISSING_DATA (1180)
Missing data section in JSON task file.

MSK_RES_ERR_JSON_NUMBER_OVERFLOW (1177)
Invalid number entry - wrong type or value overflow.

MSK_RES_ERR_JSON_STRING (1176)
Error in JSON string.

MSK_RES_ERR_JSON_SYNTAX (1175)
Syntax error in an JSON data

MSK_RES_ERR_LAST (1262)
Invalid index `last`. A given index was out of expected range.

MSK_RES_ERR_LASTI (1286)
Invalid `lasti`.

MSK_RES_ERR_LASTJ (1288)
Invalid `lastj`.

MSK_RES_ERR_LAU_ARG_K (7012)
Invalid argument `k`.

MSK_RES_ERR_LAU_ARG_M (7010)
Invalid argument `m`.

MSK_RES_ERR_LAU_ARG_N (7011)
Invalid argument `n`.

MSK_RES_ERR_LAU_ARG_TRANS (7018)
Invalid argument `trans`.

MSK_RES_ERR_LAU_ARG_TRANSA (7015)
Invalid argument `transa`.

MSK_RES_ERR_LAU_ARG_TRANSB (7016)
Invalid argument `transb`.

MSK_RES_ERR_LAU_ARG_UPLO (7017)
Invalid argument `uplo`.

MSK_RES_ERR_LAU_INVALID_LOWER_TRIANGULAR_MATRIX (7002)
An invalid lower triangular matrix.

MSK_RES_ERR_LAU_INVALID_SPARSE_SYMMETRIC_MATRIX (7019)
An invalid sparse symmetric matrix is specified. Note only the lower triangular part with no duplicates is specified.

MSK_RES_ERR_LAU_NOT_POSITIVE_DEFINITE (7001)
A matrix is not positive definite.

MSK_RES_ERR_LAU_SINGULAR_MATRIX (7000)

A matrix is singular.

MSK_RES_ERR_LAU_UNKNOWN (7005)

An unknown error.

MSK_RES_ERR_LICENSE (1000)

Invalid license.

MSK_RES_ERR_LICENSE_CANNOT_ALLOCATE (1020)

The license system cannot allocate the memory required.

MSK_RES_ERR_LICENSE_CANNOT_CONNECT (1021)

MOSEK cannot connect to the license server. Most likely the license server is not up and running.

MSK_RES_ERR_LICENSE_EXPIRED (1001)

The license has expired.

MSK_RES_ERR_LICENSE_FEATURE (1018)

A requested feature is not available in the license file(s). Most likely due to an incorrect license system setup.

MSK_RES_ERR_LICENSE_INVALID_HOSTID (1025)

The host ID specified in the license file does not match the host ID of the computer.

MSK_RES_ERR_LICENSE_MAX (1016)

Maximum number of licenses is reached.

MSK_RES_ERR_LICENSE_MOSEKLM_DAEMON (1017)

The MOSEKLM license manager daemon is not up and running.

MSK_RES_ERR_LICENSE_NO_SERVER_LINE (1028)

There is no **SERVER** line in the license file. All non-zero license count features need at least one **SERVER** line.

MSK_RES_ERR_LICENSE_NO_SERVER_SUPPORT (1027)

The license server does not support the requested feature. Possible reasons for this error include:

- The feature has expired.
- The feature's start date is later than today's date.
- The version requested is higher than feature's the highest supported version.
- A corrupted license file.

Try restarting the license and inspect the license server debug file, usually called `lmgrd.log`.

MSK_RES_ERR_LICENSE_SERVER (1015)

The license server is not responding.

MSK_RES_ERR_LICENSE_SERVER_VERSION (1026)

The version specified in the checkout request is greater than the highest version number the daemon supports.

MSK_RES_ERR_LICENSE_VERSION (1002)

The license is valid for another version of **MOSEK**.

MSK_RES_ERR_LINK_FILE_DLL (1040)

A file cannot be linked to a stream in the DLL version.

MSK_RES_ERR_LIVING_TASKS (1066)

All tasks associated with an environment must be deleted before the environment is deleted. There are still some undeleted tasks.

MSK_RES_ERR_LOWER_BOUND_IS_A_NAN (1390)

The lower bound specified is not a number (nan).

MSK_RES_ERR_LP_DUP_SLACK_NAME (1152)

The name of the slack variable added to a ranged constraint already exists.

MSK_RES_ERR_LP_EMPTY (1151)
The problem cannot be written to an LP formatted file.

MSK_RES_ERR_LP_FILE_FORMAT (1157)
Syntax error in an LP file.

MSK_RES_ERR_LP_FORMAT (1160)
Syntax error in an LP file.

MSK_RES_ERR_LP_FREE_CONSTRAINT (1155)
Free constraints cannot be written in LP file format.

MSK_RES_ERR_LP_INCOMPATIBLE (1150)
The problem cannot be written to an LP formatted file.

MSK_RES_ERR_LP_INVALID_CON_NAME (1171)
A constraint name is invalid when used in an LP formatted file.

MSK_RES_ERR_LP_INVALID_VAR_NAME (1154)
A variable name is invalid when used in an LP formatted file.

MSK_RES_ERR_LP_WRITE_CONIC_PROBLEM (1163)
The problem contains cones that cannot be written to an LP formatted file.

MSK_RES_ERR_LP_WRITE_GECO_PROBLEM (1164)
The problem contains general convex terms that cannot be written to an LP formatted file.

MSK_RES_ERR_LU_MAX_NUM_TRIES (2800)
Could not compute the LU factors of the matrix within the maximum number of allowed tries.

MSK_RES_ERR_MAX_LEN_IS_TOO_SMALL (1289)
An maximum length that is too small has been specified.

MSK_RES_ERR_MAXNUMBARVAR (1242)
The maximum number of semidefinite variables specified is smaller than the number of semidefinite variables in the task.

MSK_RES_ERR_MAXNUMCON (1240)
The maximum number of constraints specified is smaller than the number of constraints in the task.

MSK_RES_ERR_MAXNUMCONE (1304)
The value specified for `maxnumcone` is too small.

MSK_RES_ERR_MAXNUMQNZ (1243)
The maximum number of non-zeros specified for the Q matrices is smaller than the number of non-zeros in the current Q matrices.

MSK_RES_ERR_MAXNUMVAR (1241)
The maximum number of variables specified is smaller than the number of variables in the task.

MSK_RES_ERR_MIO_INTERNAL (5010)
A fatal error occurred in the mixed integer optimizer. Please contact **MOSEK** support.

MSK_RES_ERR_MIO_INVALID_NODE_OPTIMIZER (7131)
An invalid node optimizer was selected for the problem type.

MSK_RES_ERR_MIO_INVALID_ROOT_OPTIMIZER (7130)
An invalid root optimizer was selected for the problem type.

MSK_RES_ERR_MIO_NO_OPTIMIZER (1551)
No optimizer is available for the current class of integer optimization problems.

MSK_RES_ERR_MIO_NOT_LOADED (1553)
The mixed-integer optimizer is not loaded.

MSK_RES_ERR_MISSING_LICENSE_FILE (1008)
MOSEK cannot license file or a token server. See the **MOSEK** installation manual for details.

MSK_RES_ERR_MIXED_CONIC_AND_NL (1501)

The problem contains nonlinear terms conic constraints. The requested operation cannot be applied to this type of problem.

MSK_RES_ERR_MPS_CONE_OVERLAP (1118)

A variable is specified to be a member of several cones.

MSK_RES_ERR_MPS_CONE_REPEAT (1119)

A variable is repeated within the CSECTION.

MSK_RES_ERR_MPS_CONE_TYPE (1117)

Invalid cone type specified in a CSECTION.

MSK_RES_ERR_MPS_DUPLICATE_Q_ELEMENT (1121)

Duplicate elements is specified in a Q matrix.

MSK_RES_ERR_MPS_FILE (1100)

An error occurred while reading an MPS file.

MSK_RES_ERR_MPS_INV_BOUND_KEY (1108)

An invalid bound key occurred in an MPS file.

MSK_RES_ERR_MPS_INV_CON_KEY (1107)

An invalid constraint key occurred in an MPS file.

MSK_RES_ERR_MPS_INV_FIELD (1101)

A field in the MPS file is invalid. Probably it is too wide.

MSK_RES_ERR_MPS_INV_MARKER (1102)

An invalid marker has been specified in the MPS file.

MSK_RES_ERR_MPS_INV_SEC_NAME (1109)

An invalid section name occurred in an MPS file.

MSK_RES_ERR_MPS_INV_SEC_ORDER (1115)

The sections in the MPS data file are not in the correct order.

MSK_RES_ERR_MPS_INVALID_OBJ_NAME (1128)

An invalid objective name is specified.

MSK_RES_ERR_MPS_INVALID_OBJSENSE (1122)

An invalid objective sense is specified.

MSK_RES_ERR_MPS_MUL_CON_NAME (1112)

A constraint name was specified multiple times in the ROWS section.

MSK_RES_ERR_MPS_MUL_CSEC (1116)

Multiple CSECTIONs are given the same name.

MSK_RES_ERR_MPS_MUL_QOBJ (1114)

The Q term in the objective is specified multiple times in the MPS data file.

MSK_RES_ERR_MPS_MUL_QSEC (1113)

Multiple QSECTIONs are specified for a constraint in the MPS data file.

MSK_RES_ERR_MPS_NO_OBJECTIVE (1110)

No objective is defined in an MPS file.

MSK_RES_ERR_MPS_NON_SYMMETRIC_Q (1120)

A non symmetric matrice has been speciefied.

MSK_RES_ERR_MPS_NULL_CON_NAME (1103)

An empty constraint name is used in an MPS file.

MSK_RES_ERR_MPS_NULL_VAR_NAME (1104)

An empty variable name is used in an MPS file.

MSK_RES_ERR_MPS_SPLITTED_VAR (1111)

All elements in a column of the A matrix must be specified consecutively. Hence, it is illegal to specify non-zero elements in A for variable 1, then for variable 2 and then variable 1 again.

MSK_RES_ERR_MPS_TAB_IN_FIELD2 (1125)

A tab char occurred in field 2.

MSK_RES_ERR_MPS_TAB_IN_FIELD3 (1126)

A tab char occurred in field 3.

MSK_RES_ERR_MPS_TAB_IN_FIELD5 (1127)

A tab char occurred in field 5.

MSK_RES_ERR_MPS_UNDEF_CON_NAME (1105)

An undefined constraint name occurred in an MPS file.

MSK_RES_ERR_MPS_UNDEF_VAR_NAME (1106)

An undefined variable name occurred in an MPS file.

MSK_RES_ERR_MUL_A_ELEMENT (1254)

An element in A is defined multiple times.

MSK_RES_ERR_NAME_IS_NULL (1760)

The name buffer is a NULL pointer.

MSK_RES_ERR_NAME_MAX_LEN (1750)

A name is longer than the buffer that is supposed to hold it.

MSK_RES_ERR_NAN_IN_BLC (1461)

l^c contains an invalid floating point value, i.e. a NaN.

MSK_RES_ERR_NAN_IN_BLC (1471)

l^x contains an invalid floating point value, i.e. a NaN.

MSK_RES_ERR_NAN_IN_BUC (1462)

u^c contains an invalid floating point value, i.e. a NaN.

MSK_RES_ERR_NAN_IN_BUX (1472)

u^x contains an invalid floating point value, i.e. a NaN.

MSK_RES_ERR_NAN_IN_C (1470)

c contains an invalid floating point value, i.e. a NaN.

MSK_RES_ERR_NAN_IN_DOUBLE_DATA (1450)

An invalid floating point value was used in some double data.

MSK_RES_ERR_NEGATIVE_APPEND (1264)

Cannot append a negative number.

MSK_RES_ERR_NEGATIVE_SURPLUS (1263)

Negative surplus.

MSK_RES_ERR_NEWER_DLL (1036)

The dynamic link library is newer than the specified version.

MSK_RES_ERR_NO_BARS_FOR_SOLUTION (3916)

There is no \bar{s} available for the solution specified. In particular note there are no \bar{s} defined for the basic and integer solutions.

MSK_RES_ERR_NO_BARX_FOR_SOLUTION (3915)

There is no \bar{X} available for the solution specified. In particular note there are no \bar{X} defined for the basic and integer solutions.

MSK_RES_ERR_NO_BASIS_SOL (1600)

No basic solution is defined.

MSK_RES_ERR_NO_DUAL_FOR_ITG_SOL (2950)

No dual information is available for the integer solution.

- MSK_RES_ERR_NO_DUAL_INFEAS_CER (2001)**
A certificate of infeasibility is not available.
- MSK_RES_ERR_NO_INIT_ENV (1063)**
`env` is not initialized.
- MSK_RES_ERR_NO_OPTIMIZER_VAR_TYPE (1552)**
No optimizer is available for this class of optimization problems.
- MSK_RES_ERR_NO_PRIMAL_INFEAS_CER (2000)**
A certificate of primal infeasibility is not available.
- MSK_RES_ERR_NO_SNX_FOR_BAS_SOL (2953)**
 s_n^x is not available for the basis solution.
- MSK_RES_ERR_NO_SOLUTION_IN_CALLBACK (2500)**
The required solution is not available.
- MSK_RES_ERR_NON_UNIQUE_ARRAY (5000)**
An array does not contain unique elements.
- MSK_RES_ERR_NONCONVEX (1291)**
The optimization problem is nonconvex.
- MSK_RES_ERR_NONLINEAR_EQUALITY (1290)**
The model contains a nonlinear equality which defines a nonconvex set.
- MSK_RES_ERR_NONLINEAR_FUNCTIONS_NOT_ALLOWED (1428)**
An operation that is invalid for problems with nonlinear functions defined has been attempted.
- MSK_RES_ERR_NONLINEAR_RANGED (1292)**
Nonlinear constraints with finite lower and upper bound always define a nonconvex feasible set.
- MSK_RES_ERR_NR_ARGUMENTS (1199)**
Incorrect number of function arguments.
- MSK_RES_ERR_NULL_ENV (1060)**
`env` is a NULL pointer.
- MSK_RES_ERR_NULL_POINTER (1065)**
An argument to a function is unexpectedly a NULL pointer.
- MSK_RES_ERR_NULL_TASK (1061)**
`task` is a NULL pointer.
- MSK_RES_ERR_NUMCONLIM (1250)**
Maximum number of constraints limit is exceeded.
- MSK_RES_ERR_NUMVARLIM (1251)**
Maximum number of variables limit is exceeded.
- MSK_RES_ERR_OBJ_Q_NOT_NSD (1296)**
The quadratic coefficient matrix in the objective is not negative semidefinite as expected for a maximization problem. The parameter `MSK_DPAR_CHECK_CONVEXITY_REL_TOL` can be used to relax the convexity check.
- MSK_RES_ERR_OBJ_Q_NOT_PSD (1295)**
The quadratic coefficient matrix in the objective is not positive semidefinite as expected for a minimization problem. The parameter `MSK_DPAR_CHECK_CONVEXITY_REL_TOL` can be used to relax the convexity check.
- MSK_RES_ERR_OBJECTIVE_RANGE (1260)**
Empty objective range.
- MSK_RES_ERR_OLDER_DLL (1035)**
The dynamic link library is older than the specified version.
- MSK_RES_ERR_OPEN_DL (1030)**
A dynamic link library could not be opened.

MSK_RES_ERR_OPF_FORMAT (1168)

Syntax error in an OPF file

MSK_RES_ERR_OPF_NEW_VARIABLE (1169)

Introducing new variables is now allowed. When a [variables] section is present, it is not allowed to introduce new variables later in the problem.

MSK_RES_ERR_OPF_PREMATURE_EOF (1172)

Premature end of file in an OPF file.

MSK_RES_ERR_OPTIMIZER_LICENSE (1013)

The optimizer required is not licensed.

MSK_RES_ERR_OVERFLOW (1590)

A computation produced an overflow i.e. a very large number.

MSK_RES_ERR_PARAM_INDEX (1210)

Parameter index is out of range.

MSK_RES_ERR_PARAM_IS_TOO_LARGE (1215)

The parameter value is too large.

MSK_RES_ERR_PARAM_IS_TOO_SMALL (1216)

The parameter value is too small.

MSK_RES_ERR_PARAM_NAME (1205)

The parameter name is not correct.

MSK_RES_ERR_PARAM_NAME_DOUB (1206)

The parameter name is not correct for a double parameter.

MSK_RES_ERR_PARAM_NAME_INT (1207)

The parameter name is not correct for an integer parameter.

MSK_RES_ERR_PARAM_NAME_STR (1208)

The parameter name is not correct for a string parameter.

MSK_RES_ERR_PARAM_TYPE (1218)

The parameter type is invalid.

MSK_RES_ERR_PARAM_VALUE_STR (1217)

The parameter value string is incorrect.

MSK_RES_ERR_PLATFORM_NOT_LICENSED (1019)

A requested license feature is not available for the required platform.

MSK_RES_ERR_POSTSOLVE (1580)

An error occurred during the postsolve. Please contact **MOSEK** support.

MSK_RES_ERR_PROB_ITEM (1281)

An invalid problem is used.

MSK_RES_ERR_PROB_LICENSE (1006)

The software is not licensed to solve the problem.

MSK_RES_ERR_QCON_SUBI_TOO_LARGE (1409)

Invalid value in qconsubi.

MSK_RES_ERR_QCON_SUBI_TOO_SMALL (1408)

Invalid value in qconsubi.

MSK_RES_ERR_QCON_UPPER_TRIANGLE (1417)

An element in the upper triangle of a Q^k is specified. Only elements in the lower triangle should be specified.

MSK_RES_ERR_QOBJ_UPPER_TRIANGLE (1415)

An element in the upper triangle of Q^o is specified. Only elements in the lower triangle should be specified.

MSK_RES_ERR_READ_FORMAT (1090)	The specified format cannot be read.
MSK_RES_ERR_READ_LP_MISSING_END_TAG (1159)	Syntax error in LP file. Possibly missing End tag.
MSK_RES_ERR_READ_LP_NONEXISTING_NAME (1162)	A variable never occurred in objective or constraints.
MSK_RES_ERR_REMOVE_CONE_VARIABLE (1310)	A variable cannot be removed because it will make a cone invalid.
MSK_RES_ERR_REPAIR_INVALID_PROBLEM (1710)	The feasibility repair does not support the specified problem type.
MSK_RES_ERR_REPAIR_OPTIMIZATION_FAILED (1711)	Computation the optimal relaxation failed. The cause may have been numerical problems.
MSK_RES_ERR_SEN_BOUND_INVALID_LO (3054)	Analysis of lower bound requested for an index, where no lower bound exists.
MSK_RES_ERR_SEN_BOUND_INVALID_UP (3053)	Analysis of upper bound requested for an index, where no upper bound exists.
MSK_RES_ERR_SEN_FORMAT (3050)	Syntax error in sensitivity analysis file.
MSK_RES_ERR_SEN_INDEX_INVALID (3055)	Invalid range given in the sensitivity file.
MSK_RES_ERR_SEN_INDEX_RANGE (3052)	Index out of range in the sensitivity analysis file.
MSK_RES_ERR_SEN_INVALID_REGEX (3056)	Syntax error in regexp or regexp longer than 1024.
MSK_RES_ERR_SEN_NUMERICAL (3058)	Numerical difficulties encountered performing the sensitivity analysis.
MSK_RES_ERR_SEN_SOLUTION_STATUS (3057)	No optimal solution found to the original problem given for sensitivity analysis.
MSK_RES_ERR_SEN_UNDEF_NAME (3051)	An undefined name was encountered in the sensitivity analysis file.
MSK_RES_ERR_SEN_UNHANDLED_PROBLEM_TYPE (3080)	Sensitivity analysis cannot be performed for the specified problem. Sensitivity analysis is only possible for linear problems.
MSK_RES_ERR_SERVER_CONNECT (8000)	Failed to connect to remote solver server. The server string or the port string were invalid, or the server did not accept connection.
MSK_RES_ERR_SERVER_PROTOCOL (8001)	Unexpected message or data from solver server.
MSK_RES_ERR_SERVER_STATUS (8002)	Server returned non-ok HTTP status code
MSK_RES_ERR_SERVER_TOKEN (8003)	The job ID specified is incorrect or invalid
MSK_RES_ERR_SIZE_LICENSE (1005)	The problem is bigger than the license.
MSK_RES_ERR_SIZE_LICENSE_CON (1010)	The problem has too many constraints to be solved with the available license.

MSK_RES_ERR_SIZE_LICENSE_INTVAR (1012)

The problem contains too many integer variables to be solved with the available license.

MSK_RES_ERR_SIZE_LICENSE_NUMCORES (3900)

The computer contains more cpu cores than the license allows for.

MSK_RES_ERR_SIZE_LICENSE_VAR (1011)

The problem has too many variables to be solved with the available license.

MSK_RES_ERR_SOL_FILE_INVALID_NUMBER (1350)

An invalid number is specified in a solution file.

MSK_RES_ERR_SOLITEM (1237)

The solution item number `solitem` is invalid. Please note that `MSK_SOL_ITEM_SNX` is invalid for the basic solution.

MSK_RES_ERR_SOLVER_PROBTYPE (1259)

Problem type does not match the chosen optimizer.

MSK_RES_ERR_SPACE (1051)

Out of space.

MSK_RES_ERR_SPACE_LEAKING (1080)

MOSEK is leaking memory. This can be due to either an incorrect use of **MOSEK** or a bug.

MSK_RES_ERR_SPACE_NO_INFO (1081)

No available information about the space usage.

MSK_RES_ERR_SYM_MAT_DUPLICATE (3944)

A value in a symmetric matrix has been specified more than once.

MSK_RES_ERR_SYM_MAT_HUGE (1482)

A symmetric matrix contains a huge value in absolute size. The parameter `MSK_DPAR_DATA_SYM_MAT_TOL_HUGE` controls when an $e_{i,j}$ is considered huge.

MSK_RES_ERR_SYM_MAT_INVALID (1480)

A symmetric matrix contains an invalid floating point value, i.e. a NaN or an infinite value.

MSK_RES_ERR_SYM_MAT_INVALID_COL_INDEX (3941)

A column index specified for sparse symmetric matrix is invalid.

MSK_RES_ERR_SYM_MAT_INVALID_ROW_INDEX (3940)

A row index specified for sparse symmetric matrix is invalid.

MSK_RES_ERR_SYM_MAT_INVALID_VALUE (3943)

The numerical value specified in a sparse symmetric matrix is not a value floating value.

MSK_RES_ERR_SYM_MAT_NOT_LOWER_TRINGULAR (3942)

Only the lower triangular part of sparse symmetric matrix should be specified.

MSK_RES_ERR_TASK_INCOMPATIBLE (2560)

The Task file is incompatible with this platform. This results from reading a file on a 32 bit platform generated on a 64 bit platform.

MSK_RES_ERR_TASK_INVALID (2561)

The Task file is invalid.

MSK_RES_ERR_TASK_WRITE (2562)

Failed to write the task file.

MSK_RES_ERR_THREAD_COND_INIT (1049)

Could not initialize a condition.

MSK_RES_ERR_THREAD_CREATE (1048)

Could not create a thread. This error may occur if a large number of environments are created and not deleted again. In any case it is a good practice to minimize the number of environments created.

- MSK_RES_ERR_THREAD_MUTEX_INIT (1045)
Could not initialize a mutex.
- MSK_RES_ERR_THREAD_MUTEX_LOCK (1046)
Could not lock a mutex.
- MSK_RES_ERR_THREAD_MUTEX_UNLOCK (1047)
Could not unlock a mutex.
- MSK_RES_ERR_TOCONIC_CONSTR_NOT_CONIC (7153)
The constraint is not conic representable.
- MSK_RES_ERR_TOCONIC_CONSTR_Q_NOT_PSD (7150)
The matrix defining the quadratic part of constraint is not positive semidefinite.
- MSK_RES_ERR_TOCONIC_CONSTRAINT_FX (7151)
The quadratic constraint is an equality, thus not convex.
- MSK_RES_ERR_TOCONIC_CONSTRAINT_RA (7152)
The quadratic constraint has finite lower and upper bound, and therefore it is not convex.
- MSK_RES_ERR_TOCONIC_OBJECTIVE_NOT_PSD (7155)
The matrix defining the quadratic part of the objective function is not positive semidefinite.
- MSK_RES_ERR_TOO_SMALL_MAX_NUM_NZ (1245)
The maximum number of non-zeros specified is too small.
- MSK_RES_ERR_TOO_SMALL_MAXNUMANZ (1252)
The maximum number of non-zeros specified for A is smaller than the number of non-zeros in the current A .
- MSK_RES_ERR_UNB_STEP_SIZE (3100)
A step size in an optimizer was unexpectedly unbounded. For instance, if the step-size becomes unbounded in phase 1 of the simplex algorithm then an error occurs. Normally this will happen only if the problem is badly formulated. Please contact **MOSEK** support if this error occurs.
- MSK_RES_ERR_UNDEF_SOLUTION (1265)
MOSEK has the following solution types:
- an interior-point solution,
 - an basic solution,
 - and an integer solution.
- Each optimizer may set one or more of these solutions; e.g by default a successful optimization with the interior-point optimizer defines the interior-point solution, and, for linear problems, also the basic solution. This error occurs when asking for a solution or for information about a solution that is not defined.
- MSK_RES_ERR_UNDEFINED_OBJECTIVE_SENSE (1446)
The objective sense has not been specified before the optimization.
- MSK_RES_ERR_UNHANDLED_SOLUTION_STATUS (6010)
Unhandled solution status.
- MSK_RES_ERR_UNKNOWN (1050)
Unknown error.
- MSK_RES_ERR_UPPER_BOUND_IS_A_NAN (1391)
The upper bound specified is not a number (nan).
- MSK_RES_ERR_UPPER_TRIANGLE (6020)
An element in the upper triangle of a lower triangular matrix is specified.
- MSK_RES_ERR_USER_FUNC_RET (1430)
An user function reported an error.

MSK_RES_ERR_USER_FUNC_RET_DATA (1431)

An user function returned invalid data.

MSK_RES_ERR_USER_NLO_EVAL (1433)

The user-defined nonlinear function reported an error.

MSK_RES_ERR_USER_NLO_EVAL_HESSUBI (1440)

The user-defined nonlinear function reported an invalid subscript in the Hessian.

MSK_RES_ERR_USER_NLO_EVAL_HESSUBJ (1441)

The user-defined nonlinear function reported an invalid subscript in the Hessian.

MSK_RES_ERR_USER_NLO_FUNC (1432)

The user-defined nonlinear function reported an error.

MSK_RES_ERR_WHICHITEM_NOT_ALLOWED (1238)

whichitem is unacceptable.

MSK_RES_ERR_WHICHSOL (1236)

The solution defined by *whichsol* does not exists.

MSK_RES_ERR_WRITE_LP_FORMAT (1158)

Problem cannot be written as an LP file.

MSK_RES_ERR_WRITE_LP_NON_UNIQUE_NAME (1161)

An auto-generated name is not unique.

MSK_RES_ERR_WRITE_MPS_INVALID_NAME (1153)

An invalid name is created while writing an MPS file. Usually this will make the MPS file unreadable.

MSK_RES_ERR_WRITE_OPF_INVALID_VAR_NAME (1156)

Empty variable names cannot be written to OPF files.

MSK_RES_ERR_WRITING_FILE (1166)

An error occurred while writing file

MSK_RES_ERR_XML_INVALID_PROBLEM_TYPE (3600)

The problem type is not supported by the XML format.

MSK_RES_ERR_Y_IS_UNDEFINED (1449)

The solution item *y* is undefined.

9.3.3 Warning Codes

MSK_RES_WRN_ANA_ALMOST_INT_BOUNDS (904)

This warning is issued by the problem analyzer if a constraint is bound nearly integral.

MSK_RES_WRN_ANA_C_ZERO (901)

This warning is issued by the problem analyzer, if the coefficients in the linear part of the objective are all zero.

MSK_RES_WRN_ANA_CLOSE_BOUNDS (903)

This warning is issued by problem analyzer, if ranged constraints or variables with very close upper and lower bounds are detected. One should consider treating such constraints as equalities and such variables as constants.

MSK_RES_WRN_ANA_EMPTY_COLS (902)

This warning is issued by the problem analyzer, if columns, in which all coefficients are zero, are found.

MSK_RES_WRN_ANA_LARGE_BOUNDS (900)

This warning is issued by the problem analyzer, if one or more constraint or variable bounds are very large. One should consider omitting these bounds entirely by setting them to $+\text{inf}$ or $-\text{inf}$.

- MSK_RES_WRN_CONSTRUCT_INVALID_SOL_ITG (807)**
The initial value for one or more of the integer variables is not feasible.
- MSK_RES_WRN_CONSTRUCT_NO_SOL_ITG (810)**
The construct solution requires an integer solution.
- MSK_RES_WRN_CONSTRUCT_SOLUTION_INFEAS (805)**
After fixing the integer variables at the suggested values then the problem is infeasible.
- MSK_RES_WRN_DROPPED_NZ_QOBJ (201)**
One or more non-zero elements were dropped in the Q matrix in the objective.
- MSK_RES_WRN_DUPLICATE_BARVARIABLE_NAMES (852)**
Two barvariable names are identical.
- MSK_RES_WRN_DUPLICATE_CONE_NAMES (853)**
Two cone names are identical.
- MSK_RES_WRN_DUPLICATE_CONSTRAINT_NAMES (850)**
Two constraint names are identical.
- MSK_RES_WRN_DUPLICATE_VARIABLE_NAMES (851)**
Two variable names are identical.
- MSK_RES_WRN_ELIMINATOR_SPACE (801)**
The eliminator is skipped at least once due to lack of space.
- MSK_RES_WRN_EMPTY_NAME (502)**
A variable or constraint name is empty. The output file may be invalid.
- MSK_RES_WRN_IGNORE_INTEGER (250)**
Ignored integer constraints.
- MSK_RES_WRN_INCOMPLETE_LINEAR_DEPENDENCY_CHECK (800)**
The linear dependency check(s) is incomplete. Normally this is not an important warning unless the optimization problem has been formulated with linear dependencies. Linear dependencies may prevent **MOSEK** from solving the problem.
- MSK_RES_WRN_LARGE_AIJ (62)**
A numerically large value is specified for an $a_{i,j}$ element in A . The parameter **MSK_DPAR_DATA_TOL_AIJ_LARGE** controls when an $a_{i,j}$ is considered large.
- MSK_RES_WRN_LARGE_BOUND (51)**
A numerically large bound value is specified.
- MSK_RES_WRN_LARGE_CJ (57)**
A numerically large value is specified for one c_j .
- MSK_RES_WRN_LARGE_CON_FX (54)**
An equality constraint is fixed to a numerically large value. This can cause numerical problems.
- MSK_RES_WRN_LARGE_LO_BOUND (52)**
A numerically large lower bound value is specified.
- MSK_RES_WRN_LARGE_UP_BOUND (53)**
A numerically large upper bound value is specified.
- MSK_RES_WRN_LICENSE_EXPIRE (500)**
The license expires.
- MSK_RES_WRN_LICENSE_FEATURE_EXPIRE (505)**
The license expires.
- MSK_RES_WRN_LICENSE_SERVER (501)**
The license server is not responding.
- MSK_RES_WRN_LP_DROP_VARIABLE (85)**
Ignored a variable because the variable was not previously defined. Usually this implies that a variable appears in the bound section but not in the objective or the constraints.

MSK_RES_WRN_LP_OLD_QUAD_FORMAT (80)

Missing $\sqrt{2}$ after quadratic expressions in bound or objective.

MSK_RES_WRN_MIO_INFEASIBLE_FINAL (270)

The final mixed-integer problem with all the integer variables fixed at their optimal values is infeasible.

MSK_RES_WRN_MPS_SPLIT_BOU_VECTOR (72)

A BOUNDS vector is split into several nonadjacent parts in an MPS file.

MSK_RES_WRN_MPS_SPLIT_RAN_VECTOR (71)

A RANGE vector is split into several nonadjacent parts in an MPS file.

MSK_RES_WRN_MPS_SPLIT_RHS_VECTOR (70)

An RHS vector is split into several nonadjacent parts in an MPS file.

MSK_RES_WRN_NAME_MAX_LEN (65)

A name is longer than the buffer that is supposed to hold it.

MSK_RES_WRN_NO_DUALIZER (950)

No automatic dualizer is available for the specified problem. The primal problem is solved.

MSK_RES_WRN_NO_GLOBAL_OPTIMIZER (251)

No global optimizer is available.

MSK_RES_WRN_NO_NONLINEAR_FUNCTION_WRITE (450)

The problem contains a general nonlinear function in either the objective or the constraints. Such a nonlinear function cannot be written to a disk file. Note that quadratic terms when inputted explicitly can be written to disk.

MSK_RES_WRN_NZ_IN_UPR_TRI (200)

Non-zero elements specified in the upper triangle of a matrix were ignored.

MSK_RES_WRN_OPEN_PARAM_FILE (50)

The parameter file could not be opened.

MSK_RES_WRN_PARAM_IGNORED_CMIO (516)

A parameter was ignored by the conic mixed integer optimizer.

MSK_RES_WRN_PARAM_NAME_DOUB (510)

The parameter name is not recognized as a double parameter.

MSK_RES_WRN_PARAM_NAME_INT (511)

The parameter name is not recognized as an integer parameter.

MSK_RES_WRN_PARAM_NAME_STR (512)

The parameter name is not recognized as a string parameter.

MSK_RES_WRN_PARAM_STR_VALUE (515)

The string is not recognized as a symbolic value for the parameter.

MSK_RES_WRN_PRESOLVE_OUTOFSPACE (802)

The presolve is incomplete due to lack of space.

MSK_RES_WRN_QUAD_CONES_WITH_ROOT_FIXED_AT_ZERO (930)

For at least one quadratic cone the root is fixed at (nearly) zero. This may cause problems such as a very large dual solution. Therefore, it is recommended to remove such cones before optimizing the problems, or to fix all the variables in the cone to 0.

MSK_RES_WRN_RQUAD_CONES_WITH_ROOT_FIXED_AT_ZERO (931)

For at least one rotated quadratic cone at least one of the root variables are fixed at (nearly) zero. This may cause problems such as a very large dual solution. Therefore, it is recommended to remove such cones before optimizing the problems, or to fix all the variables in the cone to 0.

MSK_RES_WRN_SOL_FILE_IGNORED_CON (351)

One or more lines in the constraint section were ignored when reading a solution file.

MSK_RES_WRN_SOL_FILE_IGNORED_VAR (352)

One or more lines in the variable section were ignored when reading a solution file.

MSK_RES_WRN_SOL_FILTER (300)

Invalid solution filter is specified.

MSK_RES_WRN_SPAR_MAX_LEN (66)

A value for a string parameter is longer than the buffer that is supposed to hold it.

MSK_RES_WRN_SYM_MAT_LARGE (960)

A numerically large value is specified for an $e_{i,j}$ element in E . The parameter *MSK_DPAR_DATA_SYM_MAT_TOL_LARGE* controls when an $e_{i,j}$ is considered large.

MSK_RES_WRN_TOO_FEW_BASIS_VARS (400)

An incomplete basis has been specified. Too few basis variables are specified.

MSK_RES_WRN_TOO_MANY_BASIS_VARS (405)

A basis with too many variables has been specified.

MSK_RES_WRN_UNDEF_SOL_FILE_NAME (350)

Undefined name occurred in a solution.

MSK_RES_WRN_USING_GENERIC_NAMES (503)

Generic names are used because a name is not valid. For instance when writing an LP file the names must not contain blanks or start with a digit.

MSK_RES_WRN_WRITE_CHANGED_NAMES (803)

Some names were changed because they were invalid for the output file format.

MSK_RES_WRN_WRITE_DISCARDED_CFIX (804)

The fixed objective term could not be converted to a variable and was discarded in the output file.

MSK_RES_WRN_ZERO_AIJ (63)

One or more zero elements are specified in A .

MSK_RES_WRN_ZEROS_IN_SPARSE_COL (710)

One or more (near) zero elements are specified in a sparse column of a matrix. It is redundant to specify zero elements. Hence, it may indicate an error.

MSK_RES_WRN_ZEROS_IN_SPARSE_ROW (705)

One or more (near) zero elements are specified in a sparse row of a matrix. Since, it is redundant to specify zero elements then it may indicate an error.

9.4 Enumerations

MSKlanguagee

Language selection constants

MSK_LANG_ENG

English language selection

MSK_LANG_DAN

Danish language selection

MSKaccmodee

Constraint or variable access modes

MSK_ACC_VAR

Access data by columns (variable oriented)

MSK_ACC_CON

Access data by rows (constraint oriented)

MSKbasindtypee

Basis identification

MSK_BI_NEVER

Never do basis identification.

MSK_BI_ALWAYS

Basis identification is always performed even if the interior-point optimizer terminates abnormally.

MSK_BI_NO_ERROR

Basis identification is performed if the interior-point optimizer terminates without an error.

MSK_BI_IF_FEASIBLE

Basis identification is not performed if the interior-point optimizer terminates with a problem status saying that the problem is primal or dual infeasible.

MSK_BI_RESERVED

Not currently in use.

MSKboundkeye

Bound keys

MSK_BK_LO

The constraint or variable has a finite lower bound and an infinite upper bound.

MSK_BK_UP

The constraint or variable has an infinite lower bound and a finite upper bound.

MSK_BK_FX

The constraint or variable is fixed.

MSK_BK_FR

The constraint or variable is free.

MSK_BK_RA

The constraint or variable is ranged.

MSKmarke

Mark

MSK_MARK_LO

The lower bound is selected for sensitivity analysis.

MSK_MARK_UP

The upper bound is selected for sensitivity analysis.

MSKsimdegene

Degeneracy strategies

MSK_SIM_DEGEN_NONE

The simplex optimizer should use no degeneration strategy.

MSK_SIM_DEGEN_FREE

The simplex optimizer chooses the degeneration strategy.

MSK_SIM_DEGEN_AGGRESSIVE

The simplex optimizer should use an aggressive degeneration strategy.

MSK_SIM_DEGEN_MODERATE

The simplex optimizer should use a moderate degeneration strategy.

MSK_SIM_DEGEN_MINIMUM

The simplex optimizer should use a minimum degeneration strategy.

MSKtransposee

Transposed matrix.

MSK_TRANSPOSE_NO

No transpose is applied.

MSK_TRANSPOSE_YES

A transpose is applied.

MSKuploe

Triangular part of a symmetric matrix.

MSK_UPLO_LO

Lower part.

MSK_UPLO_UP

Upper part

MSKsimreforme

Problem reformulation.

MSK_SIM_REFORMULATION_ON

Allow the simplex optimizer to reformulate the problem.

MSK_SIM_REFORMULATION_OFF

Disallow the simplex optimizer to reformulate the problem.

MSK_SIM_REFORMULATION_FREE

The simplex optimizer can choose freely.

MSK_SIM_REFORMULATION_AGGRESSIVE

The simplex optimizer should use an aggressive reformulation strategy.

MSKsimdupvece

Exploit duplicate columns.

MSK_SIM_EXPLOIT_DUPVEC_ON

Allow the simplex optimizer to exploit duplicated columns.

MSK_SIM_EXPLOIT_DUPVEC_OFF

Disallow the simplex optimizer to exploit duplicated columns.

MSK_SIM_EXPLOIT_DUPVEC_FREE

The simplex optimizer can choose freely.

MSKsimhotstarte

Hot-start type employed by the simplex optimizer

MSK_SIM_HOTSTART_NONE

The simplex optimizer performs a coldstart.

MSK_SIM_HOTSTART_FREE

The simplex optimizer chooses the hot-start type.

MSK_SIM_HOTSTART_STATUS_KEYS

Only the status keys of the constraints and variables are used to choose the type of hot-start.

MSKintpnthotstarte

Hot-start type employed by the interior-point optimizers.

MSK_INTPNT_HOTSTART_NONE

The interior-point optimizer performs a coldstart.

MSK_INTPNT_HOTSTART_PRIMAL

The interior-point optimizer exploits the primal solution only.

MSK_INTPNT_HOTSTART_DUAL

The interior-point optimizer exploits the dual solution only.

MSK_INTPNT_HOTSTART_PRIMAL_DUAL

The interior-point optimizer exploits both the primal and dual solution.

MSKcallbackcodee

Progress call-back codes

MSK_CALLBACK_BEGIN_ROOT_CUTGEN

The call-back function is called when root cut generation is started.

MSK_CALLBACK_IM_ROOT_CUTGEN

The call-back is called from within root cut generation at an intermediate stage.

MSK_CALLBACK_END_ROOT_CUTGEN

The call-back function is called when root cut generation is terminated.

MSK_CALLBACK_BEGIN_OPTIMIZER

The call-back function is called when the optimizer is started.

MSK_CALLBACK_END_OPTIMIZER

The call-back function is called when the optimizer is terminated.

MSK_CALLBACK_BEGIN_PRESOLVE

The call-back function is called when the presolve is started.

MSK_CALLBACK_UPDATE_PRESOLVE

The call-back function is called from within the presolve procedure.

MSK_CALLBACK_IM_PRESOLVE

The call-back function is called from within the presolve procedure at an intermediate stage.

MSK_CALLBACK_END_PRESOLVE

The call-back function is called when the presolve is completed.

MSK_CALLBACK_BEGIN_INTPNT

The call-back function is called when the interior-point optimizer is started.

MSK_CALLBACK_INTPNT

The call-back function is called from within the interior-point optimizer after the information database has been updated.

MSK_CALLBACK_IM_INTPNT

The call-back function is called at an intermediate stage within the interior-point optimizer where the information database has not been updated.

MSK_CALLBACK_END_INTPNT

The call-back function is called when the interior-point optimizer is terminated.

MSK_CALLBACK_BEGIN_CONIC

The call-back function is called when the conic optimizer is started.

MSK_CALLBACK_CONIC

The call-back function is called from within the conic optimizer after the information database has been updated.

MSK_CALLBACK_IM_CONIC

The call-back function is called at an intermediate stage within the conic optimizer where the information database has not been updated.

MSK_CALLBACK_END_CONIC

The call-back function is called when the conic optimizer is terminated.

MSK_CALLBACK_PRIMAL_SIMPLEX

The call-back function is called from within the primal simplex optimizer.

MSK_CALLBACK_DUAL_SIMPLEX

The call-back function is called from within the dual simplex optimizer.

MSK_CALLBACK_BEGIN_BI

The basis identification procedure has been started.

MSK_CALLBACK_IM_BI

The call-back function is called from within the basis identification procedure at an intermediate point.

MSK_CALLBACK_END_BI

The call-back function is called when the basis identification procedure is terminated.

MSK_CALLBACK_BEGIN_PRIMAL_BI

The call-back function is called from within the basis identification procedure when the primal phase is started.

MSK_CALLBACK_IM_PRIMAL_BI

The call-back function is called from within the basis identification procedure at an intermediate point in the primal phase.

MSK_CALLBACK_UPDATE_PRIMAL_BI

The call-back function is called from within the basis identification procedure at an intermediate point in the primal phase.

MSK_CALLBACK_END_PRIMAL_BI

The call-back function is called from within the basis identification procedure when the primal phase is terminated.

MSK_CALLBACK_BEGIN_DUAL_BI

The call-back function is called from within the basis identification procedure when the dual phase is started.

MSK_CALLBACK_IM_DUAL_BI

The call-back function is called from within the basis identification procedure at an intermediate point in the dual phase.

MSK_CALLBACK_UPDATE_DUAL_BI

The call-back function is called from within the basis identification procedure at an intermediate point in the dual phase.

MSK_CALLBACK_END_DUAL_BI

The call-back function is called from within the basis identification procedure when the dual phase is terminated.

MSK_CALLBACK_BEGIN_SIMPLEX_BI

The call-back function is called from within the basis identification procedure when the simplex clean-up phase is started.

MSK_CALLBACK_IM_SIMPLEX_BI

The call-back function is called from within the basis identification procedure at an intermediate point in the simplex clean-up phase. The frequency of the call-backs is controlled by the *MSK_IPAR_LOG_SIM_FREQ* parameter.

MSK_CALLBACK_BEGIN_PRIMAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure when the primal simplex clean-up phase is started.

MSK_CALLBACK_UPDATE_PRIMAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure at an intermediate point in the primal simplex clean-up phase. The frequency of the call-backs is controlled by the *MSK_IPAR_LOG_SIM_FREQ* parameter.

MSK_CALLBACK_END_PRIMAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure when the primal clean-up phase is terminated.

MSK_CALLBACK_BEGIN_PRIMAL_DUAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure when the primal-dual simplex clean-up phase is started.

MSK_CALLBACK_UPDATE_PRIMAL_DUAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure at an intermediate point in the primal-dual simplex clean-up phase. The frequency of the call-backs is controlled by the *MSK_IPAR_LOG_SIM_FREQ* parameter.

MSK_CALLBACK_END_PRIMAL_DUAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure when the primal-dual clean-up phase is terminated.

MSK_CALLBACK_BEGIN_DUAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure when the dual simplex clean-up phase is started.

MSK_CALLBACK_UPDATE_DUAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure at an intermediate point in the dual simplex clean-up phase. The frequency of the call-backs is controlled by the *MSK_IPAR_LOG_SIM_FREQ* parameter.

MSK_CALLBACK_END_DUAL_SIMPLEX_BI

The call-back function is called from within the basis identification procedure when the dual clean-up phase is terminated.

MSK_CALLBACK_END_SIMPLEX_BI

The call-back function is called from within the basis identification procedure when the simplex clean-up phase is terminated.

MSK_CALLBACK_BEGIN_MIO

The call-back function is called when the mixed-integer optimizer is started.

MSK_CALLBACK_IM_MIO

The call-back function is called at an intermediate point in the mixed-integer optimizer.

MSK_CALLBACK_NEW_INT_MIO

The call-back function is called after a new integer solution has been located by the mixed-integer optimizer.

MSK_CALLBACK_END_MIO

The call-back function is called when the mixed-integer optimizer is terminated.

MSK_CALLBACK_BEGIN_SIMPLEX

The call-back function is called when the simplex optimizer is started.

MSK_CALLBACK_BEGIN_DUAL_SIMPLEX

The call-back function is called when the dual simplex optimizer started.

MSK_CALLBACK_IM_DUAL_SIMPLEX

The call-back function is called at an intermediate point in the dual simplex optimizer.

MSK_CALLBACK_UPDATE_DUAL_SIMPLEX

The call-back function is called in the dual simplex optimizer.

MSK_CALLBACK_END_DUAL_SIMPLEX

The call-back function is called when the dual simplex optimizer is terminated.

MSK_CALLBACK_BEGIN_PRIMAL_SIMPLEX

The call-back function is called when the primal simplex optimizer is started.

MSK_CALLBACK_IM_PRIMAL_SIMPLEX

The call-back function is called at an intermediate point in the primal simplex optimizer.

MSK_CALLBACK_UPDATE_PRIMAL_SIMPLEX

The call-back function is called in the primal simplex optimizer.

MSK_CALLBACK_END_PRIMAL_SIMPLEX

The call-back function is called when the primal simplex optimizer is terminated.

MSK_CALLBACK_BEGIN_PRIMAL_DUAL_SIMPLEX

The call-back function is called when the primal-dual simplex optimizer is started.

MSK_CALLBACK_IM_PRIMAL_DUAL_SIMPLEX

The call-back function is called at an intermediate point in the primal-dual simplex optimizer.

MSK_CALLBACK_UPDATE_PRIMAL_DUAL_SIMPLEX

The call-back function is called in the primal-dual simplex optimizer.

MSK_CALLBACK_END_PRIMAL_DUAL_SIMPLEX

The call-back function is called when the primal-dual simplex optimizer is terminated.

MSK_CALLBACK_END_SIMPLEX

The call-back function is called when the simplex optimizer is terminated.

MSK_CALLBACK_BEGIN_INFEAS_ANA

The call-back function is called when the infeasibility analyzer is started.

MSK_CALLBACK_END_INFEAS_ANA

The call-back function is called when the infeasibility analyzer is terminated.

MSK_CALLBACK_IM_PRIMAL_SENSIVITY

The call-back function is called at an intermediate stage of the primal sensitivity analysis.

MSK_CALLBACK_IM_DUAL_SENSIVITY

The call-back function is called at an intermediate stage of the dual sensitivity analysis.

MSK_CALLBACK_IM_MIO_INTPNT

The call-back function is called at an intermediate point in the mixed-integer optimizer while running the interior-point optimizer.

MSK_CALLBACK_IM_MIO_PRIMAL_SIMPLEX

The call-back function is called at an intermediate point in the mixed-integer optimizer while running the primal simplex optimizer.

MSK_CALLBACK_IM_MIO_DUAL_SIMPLEX

The call-back function is called at an intermediate point in the mixed-integer optimizer while running the dual simplex optimizer.

MSK_CALLBACK_BEGIN_PRIMAL_SETUP_BI

The call-back function is called when the primal BI setup is started.

MSK_CALLBACK_END_PRIMAL_SETUP_BI

The call-back function is called when the primal BI setup is terminated.

MSK_CALLBACK_BEGIN_DUAL_SETUP_BI

The call-back function is called when the dual BI phase is started.

MSK_CALLBACK_END_DUAL_SETUP_BI

The call-back function is called when the dual BI phase is terminated.

MSK_CALLBACK_BEGIN_PRIMAL_SENSITIVITY

Primal sensitivity analysis is started.

MSK_CALLBACK_END_PRIMAL_SENSITIVITY

Primal sensitivity analysis is terminated.

MSK_CALLBACK_BEGIN_DUAL_SENSITIVITY

Dual sensitivity analysis is started.

MSK_CALLBACK_END_DUAL_SENSITIVITY

Dual sensitivity analysis is terminated.

MSK_CALLBACK_BEGIN_LICENSE_WAIT

Begin waiting for license.

MSK_CALLBACK_END_LICENSE_WAIT

End waiting for license.

MSK_CALLBACK_IM_LICENSE_WAIT

MOSEK is waiting for a license.

MSK_CALLBACK_BEGIN_QCQO_REFORMULATE

Begin QCQO reformulation.

MSK_CALLBACK_END_QCQO_REFORMULATE

End QCQO reformulation.

MSK_CALLBACK_IM_QO_REFORMULATE

The call-back function is called at an intermediate stage of the conic quadratic reformulation.

MSK_CALLBACK_BEGIN_TO_CONIC

Begin conic reformulation.

MSK_CALLBACK_END_TO_CONIC

End conic reformulation.

MSK_CALLBACK_BEGIN_FULL_CONVEXITY_CHECK

Begin full convexity check.

MSK_CALLBACK_END_FULL_CONVEXITY_CHECK

End full convexity check.

MSK_CALLBACK_IM_FULL_CONVEXITY_CHECK

The call-back function is called at an intermediate stage of the full convexity check.

MSK_CALLBACK_BEGIN_PRIMAL_REPAIR

Begin primal feasibility repair.

MSK_CALLBACK_END_PRIMAL_REPAIR

End primal feasibility repair.

MSK_CALLBACK_BEGIN_READ

MOSEK has started reading a problem file.

MSK_CALLBACK_IM_READ

Intermediate stage in reading.

MSK_CALLBACK_END_READ

MOSEK has finished reading a problem file.

MSK_CALLBACK_BEGIN_WRITE

MOSEK has started writing a problem file.

MSK_CALLBACK_END_WRITE

MOSEK has finished writing a problem file.

MSK_CALLBACK_READ_OPF_SECTION

A chunk of Q non-zeros has been read from a problem file.

MSK_CALLBACK_IM_LU

The call-back function is called from within the LU factorization procedure at an intermediate point.

MSK_CALLBACK_IM_ORDER

The call-back function is called from within the matrix ordering procedure at an intermediate point.

MSK_CALLBACK_IM_SIMPLEX

The call-back function is called from within the simplex optimizer at an intermediate point.

MSK_CALLBACK_READ_OPF

The call-back function is called from the OPF reader.

MSK_CALLBACK_WRITE_OPF

The call-back function is called from the OPF writer.

MSK_CALLBACK_SOLVING_REMOTE

The call-back function is called while the task is being solved on a remote server.

MSKcheckconvexitytypee

Types of convexity checks.

MSK_CHECK_CONVEXITY_NONE

No convexity check.

MSK_CHECK_CONVEXITY_SIMPLE

Perform simple and fast convexity check.

MSK_CHECK_CONVEXITY_FULL

Perform a full convexity check.

MSKcompresstypee

Compression types

MSK_COMPRESS_NONE

No compression is used.

MSK_COMPRESS_FREE

The type of compression used is chosen automatically.

MSK_COMPRESS_GZIP

The type of compression used is gzip compatible.

MSKconetypee

Cone types

MSK_CT_QUAD

The cone is a quadratic cone.

MSK_CT_RQUAD

The cone is a rotated quadratic cone.

MSKnametypee

Name types

MSK_NAME_TYPE_GEN

General names. However, no duplicate and blank names are allowed.

MSK_NAME_TYPE_MPS

MPS type names.

MSK_NAME_TYPE_LP

LP type names.

MSKsymmattypee

Cone types

MSK_SYMMAT_TYPE_SPARSE

Sparse symmetric matrix.

MSKdataformate

Data format types

MSK_DATA_FORMAT_EXTENSION

The file extension is used to determine the data file format.

MSK_DATA_FORMAT_MPS

The data file is MPS formatted.

MSK_DATA_FORMAT_LP

The data file is LP formatted.

MSK_DATA_FORMAT_OP

The data file is an optimization problem formatted file.

MSK_DATA_FORMAT_XML

The data file is an XML formatted file.

MSK_DATA_FORMAT_FREE_MPS

The data a free MPS formatted file.

MSK_DATA_FORMAT_TASK
Generic task dump file.

MSK_DATA_FORMAT_CB
Conic benchmark format,

MSK_DATA_FORMAT_JSON_TASK
JSON based task format.

MSKdinfiteme
Double information items

MSK_DINF_BI_TIME
Time spent within the basis identification procedure since its invocation.

MSK_DINF_BI_PRIMAL_TIME
Time spent within the primal phase of the basis identification procedure since its invocation.

MSK_DINF_BI_DUAL_TIME
Time spent within the dual phase basis identification procedure since its invocation.

MSK_DINF_BI_CLEAN_TIME
Time spent within the clean-up phase of the basis identification procedure since its invocation.

MSK_DINF_BI_CLEAN_PRIMAL_TIME
Time spent within the primal clean-up optimizer of the basis identification procedure since its invocation.

MSK_DINF_BI_CLEAN_PRIMAL_DUAL_TIME
Time spent within the primal-dual clean-up optimizer of the basis identification procedure since its invocation.

MSK_DINF_BI_CLEAN_DUAL_TIME
Time spent within the dual clean-up optimizer of the basis identification procedure since its invocation.

MSK_DINF_INTPNT_TIME
Time spent within the interior-point optimizer since its invocation.

MSK_DINF_INTPNT_ORDER_TIME
Order time (in seconds).

MSK_DINF_INTPNT_PRIMAL_OBJ
Primal objective value reported by the interior-point optimizer.

MSK_DINF_INTPNT_DUAL_OBJ
Dual objective value reported by the interior-point optimizer.

MSK_DINF_INTPNT_PRIMAL_FEAS
Primal feasibility measure reported by the interior-point optimizers. (For the interior-point optimizer this measure does not directly related to the original problem because a homogeneous model is employed).

MSK_DINF_INTPNT_DUAL_FEAS
Dual feasibility measure reported by the interior-point optimizer. (For the interior-point optimizer this measure does not directly related to the original problem because a homogeneous model is employed.)

MSK_DINF_INTPNT_OPT_STATUS
This measure should converge to +1 if the problem has a primal-dual optimal solution, and converge to -1 if problem is (strictly) primal or dual infeasible. If the measure converges to another constant, or fails to settle, the problem is usually ill-posed.

MSK_DINF_SIM_TIME
Time spent in the simplex optimizer since invoking it.

MSK_DINF_SIM_PRIMAL_TIME
Time spent in the primal simplex optimizer since invoking it.

MSK_DINF_SIM_DUAL_TIME

Time spent in the dual simplex optimizer since invoking it.

MSK_DINF_SIM_PRIMAL_DUAL_TIME

Time spent in the primal-dual simplex optimizer since invoking it.

MSK_DINF_SIM_OBJ

Objective value reported by the simplex optimizer.

MSK_DINF_SIM_FEAS

Feasibility measure reported by the simplex optimizer.

MSK_DINF_MIO_TIME

Time spent in the mixed-integer optimizer.

MSK_DINF_MIO_ROOT PRESOLVE_TIME

Time spent in while presolving the root relaxation.

MSK_DINF_MIO_ROOT_OPTIMIZER_TIME

Time spent in the optimizer while solving the root relaxation.

MSK_DINF_MIO_OPTIMIZER_TIME

Total time spent in the optimizer.

MSK_DINF_MIO_HEURISTIC_TIME

Total time spent in the optimizer.

MSK_DINF_TO_CONIC_TIME

Time spent in the last to conic reformulation.

MSK_DINF_MIO_CONSTRUCT_SOLUTION_OBJ

If **MOSEK** has successfully constructed an integer feasible solution, then this item contains the optimal objective value corresponding to the feasible solution.

MSK_DINF_MIO_OBJ_INT

The primal objective value corresponding to the best integer feasible solution. Please note that at least one integer feasible solution must have located i.e. check | [MSK_DINF_MIO_NUM_INT_SOLUTIONS](#) |.

MSK_DINF_MIO_OBJ_BOUND

The best known bound on the objective function. This value is undefined until at least one relaxation has been solved: To see if this is the case check that | [MSK_DINF_MIO_NUM_RELAX](#) | is strictly positive.

MSK_DINF_MIO_OBJ_REL_GAP

Given that the mixed-integer optimizer has computed a feasible solution and a bound on the optimal objective value, then this item contains the relative gap defined by

$$\frac{|(\text{objective value of feasible solution}) - (\text{objective bound})|}{\max(\delta, |(\text{objective value of feasible solution})|)}.$$

where δ is given by the parameter [MSK_DPAR_MIO_REL_GAP_CONST](#). Otherwise it has the value -1.0 .

MSK_DINF_MIO_OBJ_ABS_GAP

Given the mixed-integer optimizer has computed a feasible solution and a bound on the optimal objective value, then this item contains the absolute gap defined by

$$|(\text{objective value of feasible solution}) - (\text{objective bound})|.$$

Otherwise it has the value -1.0 .

MSK_DINF_MIO_USER_OBJ_CUT

If the objective cut is used, then this information item has the value of the cut.

MSK_DINF_MIO_CMIR_SEPARATION_TIME

Separation time for CMIR cuts.

MSK_DINF_MIO_CLIQUE_SEPARATION_TIME
Seperation time for clique cuts.

MSK_DINF_MIO_KNAPSACK_COVER_SEPARATION_TIME
Seperation time for knapsack cover.

MSK_DINF_MIO_GMI_SEPARATION_TIME
Seperation time for GMI cuts.

MSK_DINF_MIO_IMPLIED_BOUND_TIME
Seperation time for implied bound cuts.

MSK_DINF_MIO_ROOT_CUTGEN_TIME
Total time for cut generation.

MSK_DINF_MIO_PROBING_TIME
Total time for probing.

MSK_DINF_OPTIMIZER_TIME
Total time spent in the optimizer since it was invoked.

MSK_DINF_PRESOLVE_TIME
Total time (in seconds) spent in the presolve since it was invoked.

MSK_DINF_MIO_DUAL_BOUND_AFTER_PRESOLVE
Value of the dual bound after presolve but before cut generation.

MSK_DINF_PRESOLVE_ELI_TIME
Total time spent in the eliminator since the presolve was invoked.

MSK_DINF_PRESOLVE_LINDEP_TIME
Total time spent in the linear dependency checker since the presolve was invoked.

MSK_DINF_RD_TIME
Time spent reading the data file.

MSK_DINF_SOL_ITR_PRIMAL_OBJ
Primal objective value of the interior-point solution.

MSK_DINF_SOL_ITR_PVIOLCON
Maximal primal bound violation for x^c in the interior-point solution.

MSK_DINF_SOL_ITR_PVIOLVAR
Maximal primal bound violation for x^x in the interior-point solution.

MSK_DINF_SOL_ITR_PVIOLBARVAR
Maximal primal bound violation for \overline{X} in the interior-point solution.

MSK_DINF_SOL_ITR_PVIOLCONES
Maximal primal violation for primal conic constraints in the interior-point solution.

MSK_DINF_SOL_ITR_DUAL_OBJ
Dual objective value of the interior-point solution.

MSK_DINF_SOL_ITR_DVIOLCON
Maximal dual bound violation for x^c in the interior-point solution.

MSK_DINF_SOL_ITR_DVIOLVAR
Maximal dual bound violation for x^x in the interior-point solution.

MSK_DINF_SOL_ITR_DVIOLBARVAR
Maximal dual bound violation for \overline{X} in the interior-point solution.

MSK_DINF_SOL_ITR_DVIOLCONES
Maximal dual violation for dual conic constraints in the interior-point solution.

MSK_DINF_SOL_ITR_NRM_XC
Infinity norm of x^c in the interior-point solution.

MSK_DINF_SOL_ITR_NRM_XX	Infinity norm of x^x in the interior-point solution.
MSK_DINF_SOL_ITR_NRM_BARX	Infinity norm of \bar{X} in the interior-point solution.
MSK_DINF_SOL_ITR_NRM_Y	Infinity norm of y in the interior-point solution.
MSK_DINF_SOL_ITR_NRM_SLC	Infinity norm of s_l^c in the interior-point solution.
MSK_DINF_SOL_ITR_NRM_SUC	Infinity norm of s_u^c in the interior-point solution.
MSK_DINF_SOL_ITR_NRM_SLX	Infinity norm of s_l^x in the interior-point solution.
MSK_DINF_SOL_ITR_NRM_SUX	Infinity norm of s_u^X in the interior-point solution.
MSK_DINF_SOL_ITR_NRM_SNX	Infinity norm of s_n^x in the interior-point solution.
MSK_DINF_SOL_ITR_NRM_BARS	Infinity norm of \bar{S} in the interior-point solution.
MSK_DINF_SOL_BAS_PRIMAL_OBJ	Primal objective value of the basic solution.
MSK_DINF_SOL_BAS_PVIOLCON	Maximal primal bound violation for x^c in the basic solution.
MSK_DINF_SOL_BAS_PVIOLVAR	Maximal primal bound violation for x^x in the basic solution.
MSK_DINF_SOL_BAS_DUAL_OBJ	Dual objective value of the basic solution.
MSK_DINF_SOL_BAS_DVIOLCON	Maximal dual bound violation for x^c in the basic solution.
MSK_DINF_SOL_BAS_DVIOLVAR	Maximal dual bound violation for x^x in the basic solution.
MSK_DINF_SOL_BAS_NRM_XC	Infinity norm of x^c in the basic solution.
MSK_DINF_SOL_BAS_NRM_XX	Infinity norm of x^x in the basic solution.
MSK_DINF_SOL_BAS_NRM_BARX	Infinity norm of \bar{X} in the basic solution.
MSK_DINF_SOL_BAS_NRM_Y	Infinity norm of y in the basic solution.
MSK_DINF_SOL_BAS_NRM_SLC	Infinity norm of s_l^c in the basic solution.
MSK_DINF_SOL_BAS_NRM_SUC	Infinity norm of s_u^c in the basic solution.
MSK_DINF_SOL_BAS_NRM_SLX	Infinity norm of s_l^x in the basic solution.
MSK_DINF_SOL_BAS_NRM_SUX	Infinity norm of s_u^X in the basic solution.

MSK_DINF_SOL_ITG_PRIMAL_OBJ
Primal objective value of the integer solution.

MSK_DINF_SOL_ITG_PVIOLCON
Maximal primal bound violation for x^c in the integer solution.

MSK_DINF_SOL_ITG_PVIOLVAR
Maximal primal bound violation for x^x in the integer solution.

MSK_DINF_SOL_ITG_PVIOLBARVAR
Maximal primal bound violation for \bar{X} in the integer solution.

MSK_DINF_SOL_ITG_PVIOLCONES
Maximal primal violation for primal conic constraints in the integer solution.

MSK_DINF_SOL_ITG_PVIOLITG
Maximal violation for the integer constraints in the integer solution.

MSK_DINF_SOL_ITG_NRM_XC
Infinity norm of x^c in the integer solution.

MSK_DINF_SOL_ITG_NRM_XX
Infinity norm of x^x in the integer solution.

MSK_DINF_SOL_ITG_NRM_BARX
Infinity norm of \bar{X} in the integer solution.

MSK_DINF_INTPNT_FACTOR_NUM_FLOPS
An estimate of the number of flops used in the factorization.

MSK_DINF_QCQO_REFORMULATE_TIME
Time spent with conic quadratic reformulation.

MSK_DINF_QCQO_REFORMULATE_MAX_PERTURBATION
Maximum absolute diagonal perturbation occurring during the QCQO reformulation.

MSK_DINF_QCQO_REFORMULATE_WORST_CHOLESKY_DIAG_SCALING
Worst Cholesky diagonal scaling.

MSK_DINF_QCQO_REFORMULATE_WORST_CHOLESKY_COLUMN_SCALING
Worst Cholesky column scaling.

MSK_DINF_PRIMAL_REPAIR_PENALTY_OBJ
The optimal objective value of the penalty function.

MSKfeaturee
License feature

MSK_FEATURE_PTS
Base system.

MSK_FEATURE_PTON
Nonlinear extension.

MSKliinfiteme
Long integer information items.

MSK_LIINF_MIO_PRE SOLVED_ANZ
Number of non-zero entries in the constraint matrix of presolved problem.

MSK_LIINF_MIO_SIMPLEX_ITER
Number of simplex iterations performed by the mixed-integer optimizer.

MSK_LIINF_MIO_INTPNT_ITER
Number of interior-point iterations performed by the mixed-integer optimizer.

MSK_LIINF_BI_PRIMAL_ITER
Number of primal pivots performed in the basis identification.

MSK_LIINF_BI_DUAL_ITER

Number of dual pivots performed in the basis identification.

MSK_LIINF_BI_CLEAN_PRIMAL_ITER

Number of primal clean iterations performed in the basis identification.

MSK_LIINF_BI_CLEAN_PRIMAL_DUAL_ITER

Number of primal-dual clean iterations performed in the basis identification.

MSK_LIINF_BI_CLEAN_DUAL_ITER

Number of dual clean iterations performed in the basis identification.

MSK_LIINF_BI_CLEAN_PRIMAL_DEG_ITER

Number of primal degenerate clean iterations performed in the basis identification.

MSK_LIINF_BI_CLEAN_PRIMAL_DUAL_SUB_ITER

Number of primal-dual subproblem clean iterations performed in the basis identification.

MSK_LIINF_BI_CLEAN_PRIMAL_DUAL_DEG_ITER

Number of primal-dual degenerate clean iterations performed in the basis identification.

MSK_LIINF_BI_CLEAN_DUAL_DEG_ITER

Number of dual degenerate clean iterations performed in the basis identification.

MSK_LIINF_INTPNT_FACTOR_NUM_NZ

Number of non-zeros in factorization.

MSK_LIINF_RD_NUMANZ

Number of non-zeros in A that is read.

MSK_LIINF_RD_NUMQNZ

Number of Q non-zeros.

MSK_LIINF_MIO_SIM_MAXITER_SETBACKS

Number of times the the simplex optimizer has hit the maximum iteration limit when re-optimizing.

MSKiinfiteme

Integer information items.

MSK_IINF_ANA_PRO_NUM_CON

Number of constraints in the problem.

MSK_IINF_ANA_PRO_NUM_CON_LO

Number of constraints with a lower bound and an infinite upper bound.

MSK_IINF_ANA_PRO_NUM_CON_UP

Number of constraints with an upper bound and an infinite lower bound.

MSK_IINF_ANA_PRO_NUM_CON_RA

Number of constraints with finite lower and upper bounds.

MSK_IINF_ANA_PRO_NUM_CON_EQ

Number of equality constraints.

MSK_IINF_ANA_PRO_NUM_CON_FR

Number of unbounded constraints.

MSK_IINF_ANA_PRO_NUM_VAR

Number of variables in the problem.

MSK_IINF_ANA_PRO_NUM_VAR_LO

Number of variables with a lower bound and an infinite upper bound.

MSK_IINF_ANA_PRO_NUM_VAR_UP

Number of variables with an upper bound and an infinite lower bound. This value is set by

MSK_IINF_ANA_PRO_NUM_VAR_RA

Number of variables with finite lower and upper bounds.

MSK_IINF_ANA_PRO_NUM_VAR_EQ	Number of fixed variables.
MSK_IINF_ANA_PRO_NUM_VAR_FR	Number of free variables.
MSK_IINF_ANA_PRO_NUM_VAR_CONT	Number of continuous variables.
MSK_IINF_ANA_PRO_NUM_VAR_BIN	Number of binary (0-1) variables.
MSK_IINF_ANA_PRO_NUM_VAR_INT	Number of general integer variables.
MSK_IINF_OPTIMIZE_RESPONSE	The response code returned by optimize.
MSK_IINF_INTPNT_ITER	Number of interior-point iterations since invoking the interior-point optimizer.
MSK_IINF_INTPNT_FACTOR_DIM_DENSE	Dimension of the dense sub system in factorization.
MSK_IINF_INTPNT_SOLVE_DUAL	Non-zero if the interior-point optimizer is solving the dual problem.
MSK_IINF_MIO_NODE_DEPTH	Depth of the last node solved.
MSK_IINF_MIO_NUMCON	Number of constraints in the problem solved by the mixed-integer optimizer.
MSK_IINF_MIO_NUMVAR	Number of variables in the problem solved by the mixed-integer optimizer.
MSK_IINF_MIO_NUMINT	Number of integer variables in the problem solved by the mixed-integer optimizer.
MSK_IINF_MIO_PRE SOLVED_NUMCONT	Number of continuous variables in the problem solved by the mixed-integer optimizer.
MSK_IINF_MIO_PRE SOLVED_NUMBIN	Number of binary variables in the problem solved by the mixed-integer optimizer.
MSK_IINF_MIO_PRE SOLVED_NUMCON	Number of constraints in the presolved problem.
MSK_IINF_MIO_PRE SOLVED_NUMVAR	Number of variables in the presolved problem.
MSK_IINF_MIO_PRE SOLVED_NUMINT	Number of integer variables in the presolved problem.
MSK_IINF_MIO_CLIQUÉ_TABLE_SIZE	Size of the clique table.
MSK_IINF_MIO_CONSTRUCT_SOLUTION	If this item has the value 0, then MOSEK did not try to construct an initial integer feasible solution. If the item has a positive value, then MOSEK successfully constructed an initial integer feasible solution.
MSK_IINF_MIO_CONSTRUCT_NUM_ROUNDINGS	Number of values in the integer solution that is rounded to an integer value.
MSK_IINF_MIO_NUM_INT_SOLUTIONS	Number of integer feasible solutions that has been found.

MSK_IINF_MIO_OBJ_BOUND_DEFINED
 Non-zero if a valid objective bound has been found, otherwise zero.

MSK_IINF_MIO_NUM_ACTIVE_NODES
 Number of active branch bound nodes.

MSK_IINF_MIO_NUM_RELAX
 Number of relaxations solved during the optimization.

MSK_IINF_MIO_NUM_BRANCH
 Number of branches performed during the optimization.

MSK_IINF_MIO_TOTAL_NUM_CUTS
 Total number of cuts generated by the mixed-integer optimizer.

MSK_IINF_MIO_NUM_CMIR_CUTS
 Number of Complemented Mixed Integer Rounding (CMIR) cuts.

MSK_IINF_MIO_NUM_CLIQUE_CUTS
 Number of clique cuts.

MSK_IINF_MIO_NUM_IMPLIED_BOUND_CUTS
 Number of implied bound cuts.

MSK_IINF_MIO_NUM_KNAPSACK_COVER_CUTS
 Number of clique cuts.

MSK_IINF_MIO_NUM_GOMORY_CUTS
 Number of Gomory cuts.

MSK_IINF_MIO_NUM_REPEATED_PRESOLVE
 Number of times presolve was repeated at root.

MSK_IINF_MIO_INITIAL_SOLUTION
 Is non-zero if an initial integer solution is specified.

MSK_IINF_MIO_USER_OBJ_CUT
 If it is non-zero, then the objective cut is used.

MSK_IINF_MIO_RELGAP_SATISFIED
 Non-zero if relative gap is within tolerances.

MSK_IINF_MIO_ABSGAP_SATISFIED
 Non-zero if absolute gap is within tolerances.

MSK_IINF_MIO_NEAR_RELGAP_SATISFIED
 Non-zero if relative gap is within relaxed tolerances.

MSK_IINF_MIO_NEAR_ABSGAP_SATISFIED
 Non-zero if absolute gap is within relaxed tolerances.

MSK_IINF_RD_PROTOTYPE
 Problem type.

MSK_IINF_RD_NUMCON
 Number of constraints read.

MSK_IINF_RD_NUMVAR
 Number of variables read.

MSK_IINF_RD_NUMBARVAR
 Number of variables read.

MSK_IINF_RD_NUMINTVAR
 Number of integer-constrained variables read.

MSK_IINF_RD_NUMQ
 Number of nonempty Q matrices read.

MSK_IINF_SIM_DUAL_DEG_ITER	The number of dual degenerate iterations.
MSK_IINF_SIM_DUAL_INF_ITER	The number of iterations taken with dual infeasibility.
MSK_IINF_SIM_DUAL_HOTSTART_LU	If 1 then a valid basis factorization of full rank was located and used by the dual simplex algorithm.
MSK_IINF_SIM_PRIMAL_ITER	Number of primal simplex iterations during the last optimization.
MSK_IINF_SIM_DUAL_ITER	Number of dual simplex iterations during the last optimization.
MSK_IINF_SIM_PRIMAL_DUAL_ITER	Number of primal dual simplex iterations during the last optimization.
MSK_IINF_INTPNT_NUM_THREADS	Number of threads that the interior-point optimizer is using.
MSK_IINF_SIM_PRIMAL_INF_ITER	The number of iterations taken with primal infeasibility.
MSK_IINF_SIM_PRIMAL_DUAL_INF_ITER	The number of master iterations with dual infeasibility taken by the primal dual simplex algorithm.
MSK_IINF_SIM_PRIMAL_DEG_ITER	The number of primal degenerate iterations.
MSK_IINF_SIM_PRIMAL_DUAL_DEG_ITER	The number of degenerate major iterations taken by the primal dual simplex algorithm.
MSK_IINF_SIM_PRIMAL_HOTSTART	If 1 then the primal simplex algorithm is solving from an advanced basis.
MSK_IINF_SIM_PRIMAL_HOTSTART_LU	If 1 then a valid basis factorization of full rank was located and used by the primal simplex algorithm.
MSK_IINF_SIM_DUAL_HOTSTART	If 1 then the dual simplex algorithm is solving from an advanced basis.
MSK_IINF_SIM_PRIMAL_DUAL_HOTSTART	If 1 then the primal dual simplex algorithm is solving from an advanced basis.
MSK_IINF_SIM_PRIMAL_DUAL_HOTSTART_LU	If 1 then a valid basis factorization of full rank was located and used by the primal dual simplex algorithm.
MSK_IINF_SOL_ITR_PROSTA	Problem status of the interior-point solution. Updated after each optimization.
MSK_IINF_SOL_ITR_SOLSTA	Solution status of the interior-point solution. Updated after each optimization.
MSK_IINF_SOL_BAS_PROSTA	Problem status of the basic solution. Updated after each optimization.
MSK_IINF_SOL_BAS_SOLSTA	Solution status of the basic solution. Updated after each optimization.
MSK_IINF_SOL_ITG_PROSTA	Problem status of the integer solution. Updated after each optimization.
MSK_IINF_SOL_ITG_SOLSTA	Solution status of the integer solution. Updated after each optimization.

MSK_IINF_SIM_NUMCON

Number of constraints in the problem solved by the simplex optimizer.

MSK_IINF_SIM_NUMVAR

Number of variables in the problem solved by the simplex optimizer.

MSK_IINF_OPT_NUMCON

Number of constraints in the problem solved when the optimizer is called.

MSK_IINF_OPT_NUMVAR

Number of variables in the problem solved when the optimizer is called

MSK_IINF_STO_NUM_A_REALLOC

Number of times the storage for storing A has been changed. A large value may indicate that memory fragmentation may occur.

MSK_IINF_RD_NUMCONE

Number of conic constraints read.

MSK_IINF_SIM_SOLVE_DUAL

Is non-zero if dual problem is solved.

MSKinfypee

Information item types

MSK_INF_DOU_TYPE

Is a double information type.

MSK_INF_INT_TYPE

Is an integer.

MSK_INF_LINT_TYPE

Is a long integer.

MSKiomodee

Input/output modes

MSK_IOMODE_READ

The file is read-only.

MSK_IOMODE_WRITE

The file is write-only. If the file exists then it is truncated when it is opened. Otherwise it is created when it is opened.

MSK_IOMODE_READWRITE

The file is to read and written.

MSKbranchdire

Specifies the branching direction.

MSK_BRANCH_DIR_FREE

The mixed-integer optimizer decides which branch to choose.

MSK_BRANCH_DIR_UP

The mixed-integer optimizer always chooses the up branch first.

MSK_BRANCH_DIR_DOWN

The mixed-integer optimizer always chooses the down branch first.

MSK_BRANCH_DIR_NEAR

Branch in direction nearest to selected fractional variable.

MSK_BRANCH_DIR_FAR

Branch in direction farthest from selected fractional variable.

MSK_BRANCH_DIR_ROOT_LP

Chose direction based on root lp value of selected variable.

MSK_BRANCH_DIR_GUIDED

Branch in direction of current incumbent.

MSK_BRANCH_DIR_PSEUDOCOST

Branch based on the pseudocost of the variable.

MSKmiocontsoltypee

Continuous mixed-integer solution type

MSK_MIO_CONT_SOL_NONE

No interior-point or basic solution are reported when the mixed-integer optimizer is used.

MSK_MIO_CONT_SOL_ROOT

The reported interior-point and basic solutions are a solution to the root node problem when mixed-integer optimizer is used.

MSK_MIO_CONT_SOL_ITG

The reported interior-point and basic solutions are a solution to the problem with all integer variables fixed at the value they have in the integer solution. A solution is only reported in case the problem has a primal feasible solution.

MSK_MIO_CONT_SOL_ITG_REL

In case the problem is primal feasible then the reported interior-point and basic solutions are a solution to the problem with all integer variables fixed at the value they have in the integer solution. If the problem is primal infeasible, then the solution to the root node problem is reported.

MSKmiomodee

Integer restrictions

MSK_MIO_MODE_IGNORED

The integer constraints are ignored and the problem is solved as a continuous problem.

MSK_MIO_MODE_SATISFIED

Integer restrictions should be satisfied.

MSKmionodeseltypee

Mixed-integer node selection types

MSK_MIO_NODE_SELECTION_FREE

The optimizer decides the node selection strategy.

MSK_MIO_NODE_SELECTION_FIRST

The optimizer employs a depth first node selection strategy.

MSK_MIO_NODE_SELECTION_BEST

The optimizer employs a best bound node selection strategy.

MSK_MIO_NODE_SELECTION_WORST

The optimizer employs a worst bound node selection strategy.

MSK_MIO_NODE_SELECTION_HYBRID

The optimizer employs a hybrid strategy.

MSK_MIO_NODE_SELECTION_PSEUDO

The optimizer employs selects the node based on a pseudo cost estimate.

MSKmpsformate

MPS file format type

MSK_MPS_FORMAT_STRICT

It is assumed that the input file satisfies the MPS format strictly.

MSK_MPS_FORMAT_RELAXED

It is assumed that the input file satisfies a slightly relaxed version of the MPS format.

MSK_MPS_FORMAT_FREE

It is assumed that the input file satisfies the free MPS format. This implies that spaces are not allowed in names. Otherwise the format is free.

MSK_MPS_FORMAT_CPLEX

The CPLEX compatible version of the MPS format is employed.

MSKmsgkeye

Message keys

MSK_MSG_READING_FILE**MSK_MSG_WRITING_FILE****MSK_MSG_MPS_SELECTED****MSKobjsensee**

Objective sense types

MSK_OBJECTIVE_SENSE_MINIMIZE

The problem should be minimized.

MSK_OBJECTIVE_SENSE_MAXIMIZE

The problem should be maximized.

MSKonoffkeye

On/off

MSK_ON

Switch the option on.

MSK_OFF

Switch the option off.

MSKoptimizertypee

Optimizer types

MSK_OPTIMIZER_FREE

The optimizer is chosen automatically.

MSK_OPTIMIZER_INTPNT

The interior-point optimizer is used.

MSK_OPTIMIZER_CONIC

The optimizer for problems having conic constraints.

MSK_OPTIMIZER_PRIMAL_SIMPLEX

The primal simplex optimizer is used.

MSK_OPTIMIZER_DUAL_SIMPLEX

The dual simplex optimizer is used.

MSK_OPTIMIZER_FREE_SIMPLEX

One of the simplex optimizers is used.

MSK_OPTIMIZER_MIXED_INT

The mixed-integer optimizer.

MSKorderingtypee

Ordering strategies

MSK_ORDER_METHOD_FREE

The ordering method is chosen automatically.

MSK_ORDER_METHOD_APPMINLOC

Approximate minimum local fill-in ordering is employed.

MSK_ORDER_METHOD_EXPERIMENTAL

This option should not be used.

MSK_ORDER_METHOD_TRY_GRAPHPAR

Always try the graph partitioning based ordering.

MSK_ORDER_METHOD_FORCE_GRAPHPAR

Always use the graph partitioning based ordering even if it is worse than the approximate minimum local fill ordering.

MSK_ORDER_METHOD_NONE

No ordering is used.

MSKpresolvemodee

Presolve method.

MSK_PRESOLVE_MODE_OFF

The problem is not presolved before it is optimized.

MSK_PRESOLVE_MODE_ON

The problem is presolved before it is optimized.

MSK_PRESOLVE_MODE_FREE

It is decided automatically whether to presolve before the problem is optimized.

MSKparametertypee

Parameter type

MSK_PAR_INVALID_TYPE

Not a valid parameter.

MSK_PAR_DOU_TYPE

Is a double parameter.

MSK_PAR_INT_TYPE

Is an integer parameter.

MSK_PAR_STR_TYPE

Is a string parameter.

MSKproblemiteme

Problem data items

MSK_PI_VAR

Item is a variable.

MSK_PI_CON

Item is a constraint.

MSK_PI_CONE

Item is a cone.

MSKproblemtypee

Problem types

MSK_PROBTYPE_LO

The problem is a linear optimization problem.

MSK_PROBTYPE_QO

The problem is a quadratic optimization problem.

MSK_PROBTYPE_QCQO

The problem is a quadratically constrained optimization problem.

MSK_PROBTYPE_GECO

General convex optimization.

MSK_PROBTYPE_CONIC

A conic optimization.

MSK_PROBTYPE_MIXED

General nonlinear constraints and conic constraints. This combination can not be solved by **MOSEK**.

MSKprostae

Problem status keys

MSK_PRO_STA_UNKNOWN

Unknown problem status.

MSK_PRO_STA_PRIM_AND_DUAL_FEAS

The problem is primal and dual feasible.

MSK_PRO_STA_PRIM_FEAS

The problem is primal feasible.

MSK_PRO_STA_DUAL_FEAS

The problem is dual feasible.

MSK_PRO_STA_NEAR_PRIM_AND_DUAL_FEAS

The problem is at least nearly primal and dual feasible.

MSK_PRO_STA_NEAR_PRIM_FEAS

The problem is at least nearly primal feasible.

MSK_PRO_STA_NEAR_DUAL_FEAS

The problem is at least nearly dual feasible.

MSK_PRO_STA_PRIM_INFEAS

The problem is primal infeasible.

MSK_PRO_STA_DUAL_INFEAS

The problem is dual infeasible.

MSK_PRO_STA_PRIM_AND_DUAL_INFEAS

The problem is primal and dual infeasible.

MSK_PRO_STA_ILL_POSED

The problem is ill-posed. For example, it may be primal and dual feasible but have a positive duality gap.

MSK_PRO_STA_PRIM_INFEAS_OR_UNBOUNDED

The problem is either primal infeasible or unbounded. This may occur for mixed-integer problems.

MSKxmlwriteroutputtypee

XML writer output mode

MSK_WRITE_XML_MODE_ROW

Write in row order.

MSK_WRITE_XML_MODE_COL

Write in column order.

MSKrescodetypee

Response code type

MSK_RESPONSE_OK

The response code is OK.

MSK_RESPONSE_WRN

The response code is a warning.

MSK_RESPONSE_TRM

The response code is an optimizer termination status.

MSK_RESPONSE_ERR

The response code is an error.

MSK_RESPONSE_UNK

The response code does not belong to any class.

MSKscalingtypee

Scaling type

MSK_SCALING_FREE

The optimizer chooses the scaling heuristic.

MSK_SCALING_NONE

No scaling is performed.

MSK_SCALING_MODERATE

A conservative scaling is performed.

MSK_SCALING_AGGRESSIVE

A very aggressive scaling is performed.

MSKscalingmethode

Scaling method

MSK_SCALING_METHOD_POW2

Scales only with power of 2 leaving the mantissa untouched.

MSK_SCALING_METHOD_FREE

The optimizer chooses the scaling heuristic.

MSKsensitivitytypee

Sensitivity types

MSK_SENSITIVITY_TYPE_BASIS

Basis sensitivity analysis is performed.

MSK_SENSITIVITY_TYPE_OPTIMAL_PARTITION

Optimal partition sensitivity analysis is performed.

MSKsimseleypee

Simplex selection strategy

MSK_SIM_SELECTION_FREE

The optimizer chooses the pricing strategy.

MSK_SIM_SELECTION_FULL

The optimizer uses full pricing.

MSK_SIM_SELECTION_ASE

The optimizer uses approximate steepest-edge pricing.

MSK_SIM_SELECTION_DEVEX

The optimizer uses devex steepest-edge pricing (or if it is not available an approximate steep-edge selection).

MSK_SIM_SELECTION_SE

The optimizer uses steepest-edge selection (or if it is not available an approximate steep-edge selection).

MSK_SIM_SELECTION_PARTIAL

The optimizer uses a partial selection approach. The approach is usually beneficial if the number of variables is much larger than the number of constraints.

MSKsoliteme

Solution items

MSK_SOL_ITEM_XC

Solution for the constraints.

MSK_SOL_ITEM_XX

Variable solution.

MSK_SOL_ITEM_Y
Lagrange multipliers for equations.

MSK_SOL_ITEM_SLC
Lagrange multipliers for lower bounds on the constraints.

MSK_SOL_ITEM_SUC
Lagrange multipliers for upper bounds on the constraints.

MSK_SOL_ITEM_SLX
Lagrange multipliers for lower bounds on the variables.

MSK_SOL_ITEM_SUX
Lagrange multipliers for upper bounds on the variables.

MSK_SOL_ITEM_SNX
Lagrange multipliers corresponding to the conic constraints on the variables.

MSKsolstae

Solution status keys

MSK_SOL_STA_UNKNOWN
Status of the solution is unknown.

MSK_SOL_STA_OPTIMAL
The solution is optimal.

MSK_SOL_STA_PRIM_FEAS
The solution is primal feasible.

MSK_SOL_STA_DUAL_FEAS
The solution is dual feasible.

MSK_SOL_STA_PRIM_AND_DUAL_FEAS
The solution is both primal and dual feasible.

MSK_SOL_STA_NEAR_OPTIMAL
The solution is nearly optimal.

MSK_SOL_STA_NEAR_PRIM_FEAS
The solution is nearly primal feasible.

MSK_SOL_STA_NEAR_DUAL_FEAS
The solution is nearly dual feasible.

MSK_SOL_STA_NEAR_PRIM_AND_DUAL_FEAS
The solution is nearly both primal and dual feasible.

MSK_SOL_STA_PRIM_INFEAS_CER
The solution is a certificate of primal infeasibility.

MSK_SOL_STA_DUAL_INFEAS_CER
The solution is a certificate of dual infeasibility.

MSK_SOL_STA_NEAR_PRIM_INFEAS_CER
The solution is almost a certificate of primal infeasibility.

MSK_SOL_STA_NEAR_DUAL_INFEAS_CER
The solution is almost a certificate of dual infeasibility.

MSK_SOL_STA_PRIM_ILLPOSED_CER
The solution is a certificate that the primal problem is illposed.

MSK_SOL_STA_DUAL_ILLPOSED_CER
The solution is a certificate that the dual problem is illposed.

MSK_SOL_STA_INTEGER_OPTIMAL
The primal solution is integer optimal.

MSK_SOL_STA_NEAR_INTEGER_OPTIMAL

The primal solution is near integer optimal.

MSKsoltypee

Solution types

MSK_SOL_BAS

The basic solution.

MSK_SOL_ITR

The interior solution.

MSK_SOL_ITG

The integer solution.

MSKsolveforme

Solve primal or dual form

MSK_SOLVE_FREE

The optimizer is free to solve either the primal or the dual problem.

MSK_SOLVE_PRIMAL

The optimizer should solve the primal problem.

MSK_SOLVE_DUAL

The optimizer should solve the dual problem.

MSKstakeye

Status keys

MSK_SK_UNK

The status for the constraint or variable is unknown.

MSK_SK_BAS

The constraint or variable is in the basis.

MSK_SK_SUPBAS

The constraint or variable is super basic.

MSK_SK_LOW

The constraint or variable is at its lower bound.

MSK_SK_UPR

The constraint or variable is at its upper bound.

MSK_SK_FIX

The constraint or variable is fixed.

MSK_SK_INF

The constraint or variable is infeasible in the bounds.

MSKstartpointtypee

Starting point types

MSK_STARTING_POINT_FREE

The starting point is chosen automatically.

MSK_STARTING_POINT_GUESS

The optimizer guesses a starting point.

MSK_STARTING_POINT_CONSTANT

The optimizer constructs a starting point by assigning a constant value to all primal and dual variables. This starting point is normally robust.

MSK_STARTING_POINT_SATISFY_BOUNDS

The starting point is chosen to satisfy all the simple bounds on nonlinear variables. If this starting point is employed, then more care than usual should be employed when choosing the bounds on the nonlinear variables. In particular very tight bounds should be avoided.

MSKstreamtypee

Stream types

MSK_STREAM_LOG

Log stream. Contains the aggregated contents of all other streams. This means that a message written to any other stream will also be written to this stream.

MSK_STREAM_MSG

Message stream. Log information relating to performance and progress of the optimization is written to this stream.

MSK_STREAM_ERR

Error stream. Error messages are written to this stream.

MSK_STREAM_WRN

Warning stream. Warning messages are written to this stream.

MSKvaluee

Integer values

MSK_MAX_STR_LEN

Maximum string length allowed in **MOSEK**.

MSK_LICENSE_BUFFER_LENGTH

The length of a license key buffer.

MSKvariabletypee

Variable types

MSK_VAR_TYPE_CONT

Is a continuous variable.

MSK_VAR_TYPE_INT

Is an integer variable.

SUPPORTED FILE FORMATS

MOSEK supports a range of problem and solution formats listed in [Table 10.1](#) and [Table 10.2](#). The **Task format** is **MOSEK**'s native binary format and it supports all features that **MOSEK** supports. The **OPF format** is **MOSEK**'s human-readable alternative that supports nearly all features (everything except semidefinite problems). In general, text formats are significantly slower to read, but can be examined and edited directly in any text editor.

Problem formats

See [Table 10.1](#).

Table 10.1: List of supported file formats for optimization problems.

Format Type	Ext.	Binary/Text	LP	QP	CQO	SDP
<i>LP</i>	lp	plain text	X	X		
<i>MPS</i>	mps	plain text	X	X		
<i>OPF</i>	opf	plain text	X	X	X	
<i>CBF</i>	cbf	plain text	X		X	X
<i>Osil</i>	xml	xml text	X	X		
<i>Task format</i>	task	binary	X	X	X	X
<i>Jtask format</i>	jtask	text	X	X	X	X

Solution formats

See [Table 10.2](#).

Table 10.2: List of supported solution formats.

Format Type	Ext.	Binary/Text	Description
<i>SOL</i>	sol	plain text	Interior Solution
	bas	plain text	Basic Solution
	int	plain text	Integer
<i>Jsol format</i>	jsol	text	Solution

Compression

MOSEK supports GZIP compression of files. Problem files with an additional `.gz` extension are assumed to be compressed when read, and are automatically compressed when written. For example, a file called

problem.mps.gz

will be considered as a GZIP compressed MPS file.

10.1 The LP File Format

MOSEK supports the LP file format with some extensions. The LP format is not a completely well-defined standard and hence different optimization packages may interpret the same LP file in slightly different ways. **MOSEK** tries to emulate as closely as possible CPLEX's behavior, but tries to stay backward compatible.

The LP file format can specify problems on the form

$$\begin{array}{ll} \text{minimize/maximize} & c^T x + \frac{1}{2} q^o(x) \\ \text{subject to} & \begin{array}{lll} l^c \leq & Ax + \frac{1}{2} q(x) & \leq u^c, \\ l^x \leq & x & \leq u^x, \\ & x_{\mathcal{J}} \text{ integer,} \end{array} \end{array}$$

where

- $x \in \mathbb{R}^n$ is the vector of decision variables.
- $c \in \mathbb{R}^n$ is the linear term in the objective.
- $q^o : \mathbb{R}^n \rightarrow \mathbb{R}$ is the quadratic term in the objective where

$$q^o(x) = x^T Q^o x$$

and it is assumed that

$$Q^o = (Q^o)^T.$$

- $A \in \mathbb{R}^{m \times n}$ is the constraint matrix.
- $l^c \in \mathbb{R}^m$ is the lower limit on the activity for the constraints.
- $u^c \in \mathbb{R}^m$ is the upper limit on the activity for the constraints.
- $l^x \in \mathbb{R}^n$ is the lower limit on the activity for the variables.
- $u^x \in \mathbb{R}^n$ is the upper limit on the activity for the variables.
- $q : \mathbb{R}^n \rightarrow \mathbb{R}$ is a vector of quadratic functions. Hence,

$$q_i(x) = x^T Q^i x$$

where it is assumed that

$$Q^i = (Q^i)^T.$$

- $\mathcal{J} \subseteq \{1, 2, \dots, n\}$ is an index set of the integer constrained variables.

10.1.1 File Sections

An LP formatted file contains a number of sections specifying the objective, constraints, variable bounds, and variable types. The section keywords may be any mix of upper and lower case letters.

Objective Function

The first section beginning with one of the keywords

```
max
maximum
maximize
min
minimum
minimize
```

defines the objective sense and the objective function, i.e.

$$c^T x + \frac{1}{2} x^T Q^o x.$$

The objective may be given a name by writing

```
myname:
```

before the expressions. If no name is given, then the objective is named `obj`.

The objective function contains linear and quadratic terms. The linear terms are written as:

```
4 x1 + x2 - 0.1 x3
```

and so forth. The quadratic terms are written in square brackets (`[]`) and are either squared or multiplied as in the examples

```
x1^2
```

and

```
x1 * x2
```

There may be zero or more pairs of brackets containing quadratic expressions.

An example of an objective section is

```
minimize
myobj: 4 x1 + x2 - 0.1 x3 + [ x1^2 + 2.1 x1 * x2 ]/2
```

Please note that the quadratic expressions are multiplied with $\frac{1}{2}$, so that the above expression means

$$\text{minimize } 4x_1 + x_2 - 0.1 \cdot x_3 + \frac{1}{2}(x_1^2 + 2.1 \cdot x_1 \cdot x_2)$$

If the same variable occurs more than once in the linear part, the coefficients are added, so that `4 x1 + 2 x1` is equivalent to `6 x1`. In the quadratic expressions `x1 * x2` is equivalent to `x2 * x1` and, as in the linear part, if the same variables multiplied or squared occur several times their coefficients are added.

Constraints

The second section beginning with one of the keywords

```
subj to
subject to
s.t.
st
```

defines the linear constraint matrix A and the quadratic matrices Q^i .

A constraint contains a name (optional), expressions adhering to the same rules as in the objective and a bound:

```
subject to
con1: x1 + x2 + [ x3^2 ]/2 <= 5.1
```

The bound type (here \leq) may be any of $<$, \leq , $=$, $>$, \geq ($<$ and \leq mean the same), and the bound may be any number.

In the standard LP format it is not possible to define more than one bound, but **MOSEK** supports defining ranged constraints by using double-colon ($::$) instead of a single-colon ($:$) after the constraint name, i.e.

$$-5 \leq x_1 + x_2 \leq 5 \tag{10.1}$$

may be written as

```
con:: -5 < x_1 + x_2 < 5
```

By default **MOSEK** writes ranged constraints this way.

If the files must adhere to the LP standard, ranged constraints must either be split into upper bounded and lower bounded constraints or be written as an equality with a slack variable. For example the expression (10.1) may be written as

$$x_1 + x_2 - sl_1 = 0, \quad -5 \leq sl_1 \leq 5.$$

Bounds

Bounds on the variables can be specified in the bound section beginning with one of the keywords

```
bound
bounds
```

The bounds section is optional but should, if present, follow the **subject to** section. All variables listed in the bounds section must occur in either the objective or a constraint.

The default lower and upper bounds are 0 and $+\infty$. A variable may be declared free with the keyword **free**, which means that the lower bound is $-\infty$ and the upper bound is $+\infty$. Furthermore it may be assigned a finite lower and upper bound. The bound definitions for a given variable may be written in one or two lines, and bounds can be any number or $\pm\infty$ (written as **+inf/-inf/+infinity/-infinity**) as in the example

```
bounds
x1 free
x2 <= 5
0.1 <= x2
x3 = 42
2 <= x4 < +inf
```

Variable Types

The final two sections are optional and must begin with one of the keywords

```
bin
binaries
binary
```

and

```
gen
general
```

Under **general** all integer variables are listed, and under **binary** all binary (integer variables with bounds 0 and 1) are listed:

```

general
x1 x2
binary
x3 x4

```

Again, all variables listed in the binary or general sections must occur in either the objective or a constraint.

Terminating Section

Finally, an LP formatted file must be terminated with the keyword

```
end
```

10.1.2 LP File Examples

Linear example lo1.lp

```

\ File: lo1.lp
maximize
obj: 3 x1 + x2 + 5 x3 + x4
subject to
c1: 3 x1 + x2 + 2 x3 = 30
c2: 2 x1 + x2 + 3 x3 + x4 >= 15
c3: 2 x2 + 3 x4 <= 25
bounds
0 <= x1 <= +infinity
0 <= x2 <= 10
0 <= x3 <= +infinity
0 <= x4 <= +infinity
end

```

Mixed integer example milo1.lp

```

maximize
obj: x1 + 6.4e-01 x2
subject to
c1: 5e+01 x1 + 3.1e+01 x2 <= 2.5e+02
c2: 3e+00 x1 - 2e+00 x2 >= -4e+00
bounds
0 <= x1 <= +infinity
0 <= x2 <= +infinity
general
x1 x2
end

```

10.1.3 LP Format peculiarities

Comments

Anything on a line after a \ is ignored and is treated as a comment.

Names

A name for an objective, a constraint or a variable may contain the letters *a-z*, *A-Z*, the digits *0-9* and the characters

!"#\$%&()/,.;?@_`'|~

The first character in a name must not be a number, a period or the letter *e* or *E*. Keywords must not be used as names.

MOSEK accepts any character as valid for names, except `\0`. A name that is not allowed in LP file will be changed and a warning will be issued.

The algorithm for making names LP valid works as follows: The name is interpreted as an `utf-8` string. For a unicode character *c*:

- If *c*==`_` (underscore), the output is `__` (two underscores).
- If *c* is a valid LP name character, the output is just *c*.
- If *c* is another character in the ASCII range, the output is `_XX`, where *XX* is the hexadecimal code for the character.
- If *c* is a character in the range *127-65535*, the output is `_uXXXX`, where *XXXX* is the hexadecimal code for the character.
- If *c* is a character above 65535, the output is `_UXXXXXXXX`, where *XXXXXXXX* is the hexadecimal code for the character.

Invalid `utf-8` substrings are escaped as `_XX'`, and if a name starts with a period, *e* or *E*, that character is escaped as `_XX`.

Variable Bounds

Specifying several upper or lower bounds on one variable is possible but **MOSEK** uses only the tightest bounds. If a variable is fixed (with `=`), then it is considered the tightest bound.

MOSEK Extensions to the LP Format

Some optimization software packages employ a more strict definition of the LP format than the one used by **MOSEK**. The limitations imposed by the strict LP format are the following:

- Quadratic terms in the constraints are not allowed.
- Names can be only 16 characters long.
- Lines must not exceed 255 characters in length.

If an LP formatted file created by **MOSEK** should satisfy the strict definition, then the parameter

- `MSK_IPAR_WRITE_LP_STRICT_FORMAT`

should be set; note, however, that some problems cannot be written correctly as a strict LP formatted file. For instance, all names are truncated to 16 characters and hence they may lose their uniqueness and change the problem.

To get around some of the inconveniences converting from other problem formats, **MOSEK** allows lines to contain 1024 characters and names may have any length (shorter than the 1024 characters).

Internally in **MOSEK** names may contain any (printable) character, many of which cannot be used in LP names. Setting the parameters

- `MSK_IPAR_READ_LP_QUOTED_NAMES` and
- `MSK_IPAR_WRITE_LP_QUOTED_NAMES`

allows **MOSEK** to use quoted names. The first parameter tells **MOSEK** to remove quotes from quoted names e.g, "x1", when reading LP formatted files. The second parameter tells **MOSEK** to put quotes around any semi-illegal name (names beginning with a number or a period) and fully illegal name (containing illegal characters). As double quote is a legal character in the LP format, quoting semi-illegal names makes them legal in the pure LP format as long as they are still shorter than 16 characters. Fully illegal names are still illegal in a pure LP file.

10.1.4 The strict LP format

The LP format is not a formal standard and different vendors have slightly different interpretations of the LP format. To make **MOSEK**'s definition of the LP format more compatible with the definitions of other vendors, use the parameter setting

- `MSK_IPAR_WRITE_LP_STRICT_FORMAT = MSK_ON`

This setting may lead to truncation of some names and hence to an invalid LP file. The simple solution to this problem is to use the parameter setting

- `MSK_IPAR_WRITE_GENERIC_NAMES = MSK_ON`

which will cause all names to be renamed systematically in the output file.

10.1.5 Formatting of an LP File

A few parameters control the visual formatting of LP files written by **MOSEK** in order to make it easier to read the files. These parameters are

- `MSK_IPAR_WRITE_LP_LINE_WIDTH`
- `MSK_IPAR_WRITE_LP_TERMS_PER_LINE`

The first parameter sets the maximum number of characters on a single line. The default value is 80 corresponding roughly to the width of a standard text document.

The second parameter sets the maximum number of terms per line; a term means a sign, a coefficient, and a name (for example + 42 elephants). The default value is 0, meaning that there is no maximum.

Unnamed Constraints

Reading and writing an LP file with **MOSEK** may change it superficially. If an LP file contains unnamed constraints or objective these are given their generic names when the file is read (however unnamed constraints in **MOSEK** are written without names).

10.2 The MPS File Format

MOSEK supports the standard MPS format with some extensions. For a detailed description of the MPS format see the book by Nazareth [Naz87].

10.2.1 MPS File Structure

The version of the MPS format supported by **MOSEK** allows specification of an optimization problem of the form

$$\begin{aligned} l^c &\leq Ax + q(x) &\leq u^c, \\ l^x &\leq x &\leq u^x, \\ x &\in \mathcal{K}, \\ x_{\mathcal{J}} &\text{ integer,} \end{aligned} \tag{10.2}$$

where

- $x \in \mathbb{R}^n$ is the vector of decision variables.
- $A \in \mathbb{R}^{m \times n}$ is the constraint matrix.
- $l^c \in \mathbb{R}^m$ is the lower limit on the activity for the constraints.
- $u^c \in \mathbb{R}^m$ is the upper limit on the activity for the constraints.
- $l^x \in \mathbb{R}^n$ is the lower limit on the activity for the variables.
- $u^x \in \mathbb{R}^n$ is the upper limit on the activity for the variables.
- $q : \mathbb{R}^n \rightarrow \mathbb{R}$ is a vector of quadratic functions. Hence,

$$q_i(x) = \frac{1}{2} x^T Q^i x$$

where it is assumed that

$$Q^i = (Q^i)^T.$$

Please note the explicit $\frac{1}{2}$ in the quadratic term and that Q^i is required to be symmetric.

- \mathcal{K} is a convex cone.
- $\mathcal{J} \subseteq \{1, 2, \dots, n\}$ is an index set of the integer-constrained variables.

An MPS file with one row and one column can be illustrated like this:

```
*          1          2          3          4          5          6
*23456789012345678901234567890123456789012345678901234567890
NAME          [name]
OBJSENSE
[objsense]
OBJNAME
[objname]
ROWS
? [cname1]
COLUMNS
[vname1] [cname1] [value1] [vname3] [value2]
RHS
[name] [cname1] [value1] [cname2] [value2]
RANGES
[name] [cname1] [value1] [cname2] [value2]
QSECTION [cname1]
[vname1] [vname2] [value1] [vname3] [value2]
QMATRIX
[vname1] [vname2] [value1]
QUADOBJ
[vname1] [vname2] [value1]
QCMATRIX [cname1]
[vname1] [vname2] [value1]
BOUNDS
?? [name] [vname1] [value1]
CSECTION [kname1] [value1] [ktype]
[vname1]
ENDATA
```

Here the names in capitals are keywords of the MPS format and names in brackets are custom defined names or values. A couple of notes on the structure:

- Fields: All items surrounded by brackets appear in *fields*. The fields named “valueN” are numerical values. Hence, they must have the format

```
[+|-]XXXXXXXX.XXXXXX[[e|E][+|-]XXX]
```

where

```
.. code-block:: text
```

```
X = [0|1|2|3|4|5|6|7|8|9].
```

- Sections: The MPS file consists of several sections where the names in capitals indicate the beginning of a new section. For example, COLUMNS denotes the beginning of the columns section.
- Comments: Lines starting with an * are comment lines and are ignored by **MOSEK**.
- Keys: The question marks represent keys to be specified later.
- Extensions: The sections QSECTION and CSECTION are specific **MOSEK** extensions of the MPS format. The sections QMATRIX, QUADOBJ and QCMATRIX are included for sake of compatibility with other vendors extensions to the MPS format.

The standard MPS format is a fixed format, i.e. everything in the MPS file must be within certain fixed positions. **MOSEK** also supports a *free format*. See Section 10.2.9 for details.

Linear example lo1.mps

A concrete example of a MPS file is presented below:

```
* File: lo1.mps
NAME          lo1
OBJSENSE
    MAX
ROWS
N  obj
E  c1
G  c2
L  c3
COLUMNS
    x1      obj      3
    x1      c1       3
    x1      c2       2
    x2      obj      1
    x2      c1       1
    x2      c2       1
    x2      c3       2
    x3      obj      5
    x3      c1       2
    x3      c2       3
    x4      obj      1
    x4      c2       1
    x4      c3       3
RHS
    rhs     c1      30
    rhs     c2      15
    rhs     c3      25
RANGES
BOUNDS
UP bound    x2      10
ENDATA
```

Subsequently each individual section in the MPS format is discussed.

Section NAME

In this section a name ([name]) is assigned to the problem.

OBJSENSE (optional)

This is an optional section that can be used to specify the sense of the objective function. The **OBJSENSE** section contains one line at most which can be one of the following

```
MIN
MINIMIZE
MAX
MAXIMIZE
```

It should be obvious what the implication is of each of these four lines.

OBJNAME (optional)

This is an optional section that can be used to specify the name of the row that is used as objective function. The **OBJNAME** section contains one line at most which has the form

```
objname
```

`objname` should be a valid row name.

ROWS

A record in the **ROWS** section has the form

```
? [cname1]
```

where the requirements for the fields are as follows:

Field	Starting Position	Max Width	required	Description
?	2	1	Yes	Constraint key
[cname1]	5	8	Yes	Constraint name

Hence, in this section each constraint is assigned an unique name denoted by `[cname1]`. Please note that `[cname1]` starts in position 5 and the field can be at most 8 characters wide. An initial key ? must be present to specify the type of the constraint. The key can have the values E, G, L, or N with the following interpretation:

Constraint type	l_i^c	u_i^c
E	finite	l_i^c
G	finite	∞
L	$-\infty$	finite
N	$-\infty$	∞

In the MPS format an objective vector is not specified explicitly, but one of the constraints having the key N will be used as the objective vector c . In general, if multiple N type constraints are specified, then the first will be used as the objective vector c .

COLUMNS

In this section the elements of A are specified using one or more records having the form:

```
[vname1] [cname1] [value1] [cname2] [value2]
```

where the requirements for each field are as follows:

Field	Starting Position	Max Width	required	Description
[vname1]	5	8	Yes	Variable name
[cname1]	15	8	Yes	Constraint name
[value1]	25	12	Yes	Numerical value
[cname2]	40	8	No	Constraint name
[value2]	50	12	No	Numerical value

Hence, a record specifies one or two elements a_{ij} of A using the principle that [vname1] and [cname1] determines j and i respectively. Please note that [cname1] must be a constraint name specified in the ROWS section. Finally, [value1] denotes the numerical value of a_{ij} . Another optional element is specified by [cname2], and [value2] for the variable specified by [vname1]. Some important comments are:

- All elements belonging to one variable must be grouped together.
- Zero elements of A should not be specified.
- At least one element for each variable should be specified.

RHS (optional)

A record in this section has the format

[name]	[cname1]	[value1]	[cname2]	[value2]
--------	----------	----------	----------	----------

where the requirements for each field are as follows:

Field	Starting Position	Max Width	required	Description
[name]	5	8	Yes	Name of the RHS vector
[cname1]	15	8	Yes	Constraint name
[value1]	25	12	Yes	Numerical value
[cname2]	40	8	No	Constraint name
[value2]	50	12	No	Numerical value

The interpretation of a record is that [name] is the name of the RHS vector to be specified. In general, several vectors can be specified. [cname1] denotes a constraint name previously specified in the ROWS section. Now, assume that this name has been assigned to the i th constraint and v_1 denotes the value specified by [value1], then the interpretation of v_1 is:

Constraint	l_i^c	u_i^c
type		
E	v_1	v_1
G	v_1	
L		v_1
N		

An optional second element is specified by [cname2] and [value2] and is interpreted in the same way. Please note that it is not necessary to specify zero elements, because elements are assumed to be zero.

RANGES (optional)

A record in this section has the form

[name]	[cname1]	[value1]	[cname2]	[value2]
--------	----------	----------	----------	----------

where the requirements for each fields are as follows:

Field	Starting Position	Max Width	required	Description
[name]	5	8	Yes	Name of the RANGE vector
[cname1]	15	8	Yes	Constraint name
[value1]	25	12	Yes	Numerical value
[cname2]	40	8	No	Constraint name
[value2]	50	12	No	Numerical value

The records in this section are used to modify the bound vectors for the constraints, i.e. the values in l^c and u^c . A record has the following interpretation: [name] is the name of the RANGE vector and [cname1] is a valid constraint name. Assume that [cname1] is assigned to the i th constraint and let v_1 be the value specified by [value1], then a record has the interpretation:

Constraint type	Sign of v_1	l_i^c	u_i^c
E	—	$u_i^c + v_1$	
E	+		$l_i^c + v_1$
G	— or +	$l_i^c + v_1 $	
L	— or +	$u_i^c - v_1 $	
N			

QSECTION (optional)

Within the QSECTION the label [cname1] must be a constraint name previously specified in the ROWS section. The label [cname1] denotes the constraint to which the quadratic term belongs. A record in the QSECTION has the form

[vname1]	[vname2]	[value1]	[vname3]	[value2]
----------	----------	----------	----------	----------

where the requirements for each field are:

Field	Starting Position	Max Width	required	Description
[vname1]	5	8	Yes	Variable name
[vname2]	15	8	Yes	Variable name
[value1]	25	12	Yes	Numerical value
[vname3]	40	8	No	Variable name
[value2]	50	12	No	Numerical value

A record specifies one or two elements in the lower triangular part of the Q^i matrix where [cname1] specifies the i . Hence, if the names [vname1] and [vname2] have been assigned to the k th and j th variable, then Q_{kj}^i is assigned the value given by [value1]. An optional second element is specified in the same way by the fields [vname1], [vname3], and [value2].

The example

$$\begin{array}{ll} \text{minimize} & -x_2 + \frac{1}{2}(2x_1^2 - 2x_1x_3 + 0.2x_2^2 + 2x_3^2) \\ \text{subject to} & x_1 + x_2 + x_3 \geq 1, \\ & x \geq 0 \end{array}$$

has the following MPS file representation

```
* File: qo1.mps
NAME          qo1
ROWS
N  obj
G  c1
COLUMNS
x1      c1      1.0
x2      obj     -1.0
x2      c1      1.0
x3      c1      1.0
RHS
rhs      c1      1.0
QSECTION      obj
x1      x1      2.0
x1      x3     -1.0
x2      x2      0.2
x3      x3      2.0
ENDATA
```

Regarding the QSECTIONS please note that:

- Only one QSECTION is allowed for each constraint.
- The QSECTIONS can appear in an arbitrary order after the COLUMNS section.
- All variable names occurring in the QSECTION must already be specified in the COLUMNS section.
- All entries specified in a QSECTION are assumed to belong to the lower triangular part of the quadratic term of Q .

QMATRIX/QUADOBJ (optional)

The QMATRIX and QUADOBJ sections allow to define the quadratic term of the objective function. They differ in how the quadratic term of the objective function is stored:

- QMATRIX It stores all the nonzeros coefficients, without taking advantage of the symmetry of the Q matrix.
- QUADOBJ It only store the upper diagonal nonzero elements of the Q matrix.

A record in both sections has the form:

[vname1]	[vname2]	[value1]
----------	----------	----------

where the requirements for each field are:

Field	Starting Position	Max Width	required	Description
[vname1]	5	8	Yes	Variable name
[vname2]	15	8	Yes	Variable name
[value1]	25	12	Yes	Numerical value

A record specifies one elements of the Q matrix in the objective function. Hence, if the names [vname1] and [vname2] have been assigned to the k th and j th variable, then Q_{kj} is assigned the value given by [value1]. Note that a line must appear for each off-diagonal coefficient if using a QMATRIX section, while only one entry is required in a QUADOBJ section. The quadratic part of the objective function will be evaluated as $1/2x^T Qx$.

The example

$$\begin{aligned}
 &\text{minimize} && -x_2 + \frac{1}{2}(2x_1^2 - 2x_1x_3 + 0.2x_2^2 + 2x_3^2) \\
 &\text{subject to} && x_1 + x_2 + x_3 \geq 1, \\
 &&& x \geq 0
 \end{aligned}$$

has the following MPS file representation using QMATRIX

```

* File: qo1_matrix.mps
NAME          qo1_qmatrix
ROWS
  N  obj
  G  c1
COLUMNS
  x1      c1      1.0
  x2      obj     -1.0
  x2      c1      1.0
  x3      c1      1.0
RHS
  rhs     c1      1.0
QMATRIX
  x1      x1      2.0
  x1      x3     -1.0
  x3      x1     -1.0
  x2      x2      0.2
  x3      x3      2.0
ENDATA

```

or the following using QUADOBJ

```
* File: qo1_quadobj.mps
NAME          qo1_quadobj
ROWS
  N  obj
  G  c1
COLUMNS
  x1      c1      1.0
  x2      obj     -1.0
  x2      c1      1.0
  x3      c1      1.0
RHS
  rhs     c1      1.0
QUADOBJ
  x1      x1      2.0
  x1      x3     -1.0
  x2      x2      0.2
  x3      x3      2.0
ENDATA
```

Please also note that:

- A QMATRIX/QUADOBJ section can appear in an arbitrary order after the COLUMNS section.
- All variable names occurring in the QMATRIX/QUADOBJ section must already be specified in the COLUMNS section.

10.2.2 QCMATRIX (optional)

A QCMATRIX section allows to specify the quadratic part of a given constraints. Within the QCMATRIX the label [cname1] must be a constraint name previously specified in the ROWS section. The label [cname1] denotes the constraint to which the quadratic term belongs. A record in the QSECTION has the form

[vname1]	[vname2]	[value1]
----------	----------	----------

where the requirements for each field are:

Field	Starting Position	Max Width	required	Description
[vname1]	5	8	Yes	Variable name
[vname2]	15	8	Yes	Variable name
[value1]	25	12	Yes	Numerical value

A record specifies an entry of the Q^i matrix where [cname1] specifies the i . Hence, if the names [vname1] and [vname2] have been assigned to the k th and j th variable, then Q_{kj}^i is assigned the value given by [value1]. Moreover, the quadratic term is represented as $1/2x^T Qx$.

The example

$$\begin{aligned}
 &\text{minimize} && x_2 \\
 &\text{subject to} && x_1 + x_2 + x_3 \geq 1, \\
 & && \frac{1}{2}(-2x_1x_3 + 0.2x_2^2 + 2x_3^2) \leq 10, \\
 & && x \geq 0
 \end{aligned}$$

has the following MPS file representation

```
* File: qo1.mps
NAME          qo1
ROWS
  N  obj
  G  c1
  L  q1
COLUMNS
```


x1	c1	1.0
x2	obj	-1.0
x2	c1	1.0
x3	c1	1.0
RHS		
rhs	c1	1.0
rhs	q1	10.0
QCMATRIX		
	q1	
x1	x1	2.0
x1	x3	-1.0
x3	x1	-1.0
x2	x2	0.2
x3	x3	2.0
ENDATA		

Regarding the QCMATRIXs please note that:

- Only one QCMATRIX is allowed for each constraint.
- The QCMATRIXs can appear in an arbitrary order after the COLUMNS section.
- All variable names occurring in the QSECTION must already be specified in the COLUMNS section.
- A QCMATRIX does not exploit the symmetry of Q : an off-diagonal entry (i, j) should appear twice.

10.2.3 BOUNDS (optional)

In the BOUNDS section changes to the default bounds vectors l^x and u^x are specified. The default bounds vectors are $l^x = 0$ and $u^x = \infty$. Moreover, it is possible to specify several sets of bound vectors. A record in this section has the form

??	[name]	[vname1]	[value1]
----	--------	----------	----------

where the requirements for each field are:

Field	Starting Position	Max Width	Required	Description
??	2	2	Yes	Bound key
[name]	5	8	Yes	Name of the BOUNDS vector
[vname1]	15	8	Yes	Variable name
[value1]	25	12	No	Numerical value

Hence, a record in the BOUNDS section has the following interpretation: [name] is the name of the bound vector and [vname1] is the name of the variable which bounds are modified by the record. ?? and [value1] are used to modify the bound vectors according to the following table:

??	l_j^x	u_j^x	Made integer (added to \mathcal{J})
FR	$-\infty$	∞	No
FX	v_1	v_1	No
LO	v_1	unchanged	No
MI	$-\infty$	unchanged	No
PL	unchanged	∞	No
UP	unchanged	v_1	No
BV	0	1	Yes
LI	$\lceil v_1 \rceil$	unchanged	Yes
UI	unchanged	$\lfloor v_1 \rfloor$	Yes

v_1 is the value specified by [value1].

10.2.4 CSECTION (optional)

The purpose of the CSECTION is to specify the constraint

$$x \in \mathcal{K}.$$

in (10.2). It is assumed that \mathcal{K} satisfies the following requirements. Let

$$x^t \in \mathbb{R}^{n^t}, \quad t = 1, \dots, k$$

be vectors comprised of parts of the decision variables x so that each decision variable is a member of exactly **one** vector x^t , for example

$$x^1 = \begin{bmatrix} x_1 \\ x_4 \\ x_7 \end{bmatrix} \quad \text{and} \quad x^2 = \begin{bmatrix} x_6 \\ x_5 \\ x_3 \\ x_2 \end{bmatrix}.$$

Next define

$$\mathcal{K} := \{x \in \mathbb{R}^n : \quad x^t \in \mathcal{K}_t, \quad t = 1, \dots, k\}$$

where \mathcal{K}_t must have one of the following forms

- \mathbb{R} set:

$$\mathcal{K}_t = \{x \in \mathbb{R}^{n^t}\}.$$

- Quadratic cone:

$$\mathcal{K}_t = \left\{ x \in \mathbb{R}^{n^t} : x_1 \geq \sqrt{\sum_{j=2}^{n^t} x_j^2} \right\}. \quad (10.3)$$

- Rotated quadratic cone:

$$\mathcal{K}_t = \left\{ x \in \mathbb{R}^{n^t} : 2x_1x_2 \geq \sum_{j=3}^{n^t} x_j^2, \quad x_1, x_2 \geq 0 \right\}. \quad (10.4)$$

In general, only quadratic and rotated quadratic cones are specified in the MPS file whereas membership of the \mathbb{R} set is not. If a variable is not a member of any other cone then it is assumed to be a member of an \mathbb{R} cone.

Next, let us study an example. Assume that the quadratic cone

$$x_4 \geq \sqrt{x_5^2 + x_8^2}$$

and the rotated quadratic cone

$$x_3x_7 \geq x_1^2 + x_0^2, \quad x_3, x_7 \geq 0,$$

should be specified in the MPS file. One CSECTION is required for each cone and they are specified as follows:

*	1	2	3	4	5	6
*234567890123456789012345678901234567890123456789012345678901234567890						
CSECTION	konea	0.0	QUAD			
x4						
x5						
x8						
CSECTION	koneb	0.0	RQUAD			
x7						
x3						
x1						
x0						

This first CSECTION specifies the cone (10.3) which is given the name `konea`. This is a quadratic cone which is specified by the keyword `QUAD` in the CSECTION header. The 0.0 value in the CSECTION header is not used by the `QUAD` cone.

The second CSECTION specifies the rotated quadratic cone (10.4). Please note the keyword `RQUAD` in the CSECTION which is used to specify that the cone is a rotated quadratic cone instead of a quadratic cone. The 0.0 value in the CSECTION header is not used by the `RQUAD` cone.

In general, a CSECTION header has the format

CSECTION	[kname1]	[value1]	[ktype]
----------	----------	----------	---------

where the requirement for each field are as follows:

Field	Starting Position	Max Width	Required	Description
[kname1]	5	8	Yes	Name of the cone
[value1]	15	12	No	Cone parameter
[ktype]	25		Yes	Type of the cone.

The possible cone type keys are:

Cone type key	Members	Interpretation.
QUAD	≤ 1	Quadratic cone i.e. (10.3).
RQUAD	≤ 2	Rotated quadratic cone i.e. (10.4).

Please note that a quadratic cone must have at least one member whereas a rotated quadratic cone must have at least two members. A record in the CSECTION has the format

[vname1]

where the requirements for each field are

Field	Starting Position	Max Width	required	Description
[vname1]	2	8	Yes	A valid variable name

The most important restriction with respect to the CSECTION is that a variable must occur in only one CSECTION.

10.2.5 ENDATA

This keyword denotes the end of the MPS file.

10.2.6 Integer Variables

Using special bound keys in the BOUNDS section it is possible to specify that some or all of the variables should be integer-constrained i.e. be members of \mathcal{J} . However, an alternative method is available.

This method is available only for backward compatibility and we recommend that it is not used. This method requires that markers are placed in the COLUMNS section as in the example:

```
COLUMNS
x1      obj      -10.0          c1      0.7
x1      c2        0.5          c3      1.0
x1      c4        0.1
* Start of integer-constrained variables.
MARK000 'MARKER'              'INTORG'
x2      obj      -9.0          c1      1.0
x2      c2      0.833333333333 c3      0.666666667
x2      c4        0.25
x3      obj      1.0          c6      2.0
MARK001 'MARKER'              'INTEND'
```

- End of integer-constrained variables.

Please note that special marker lines are used to indicate the start and the end of the integer variables. Furthermore be aware of the following

- **IMPORTANT:** All variables between the markers are assigned a default lower bound of 0 and a default upper bound of 1. **This may not be what is intended.** If it is not intended, the correct bounds should be defined in the `BOUNDS` section of the MPS formatted file.
- **MOSEK** ignores field 1, i.e. `MARK0001` and `MARK001`, however, other optimization systems require them.
- Field 2, i.e. `MARKER`, must be specified including the single quotes. This implies that no row can be assigned the name `MARKER`.
- Field 3 is ignored and should be left blank.
- Field 4, i.e. `INTORG` and `INTEND`, must be specified.
- It is possible to specify several such integer marker sections within the `COLUMNS` section.

10.2.7 General Limitations

- An MPS file should be an ASCII file.

10.2.8 Interpretation of the MPS Format

Several issues related to the MPS format are not well-defined by the industry standard. However, **MOSEK** uses the following interpretation:

- If a matrix element in the `COLUMNS` section is specified multiple times, then the multiple entries are added together.
- If a matrix element in a `QSECTION` section is specified multiple times, then the multiple entries are added together.

10.2.9 The Free MPS Format

MOSEK supports a free format variation of the MPS format. The free format is similar to the MPS file format but less restrictive, e.g. it allows longer names. However, it also presents two main limitations:

- A name must not contain any blanks.
- By default a line in the MPS file must not contain more than 1024 characters. However, by modifying the parameter `MSK_IPAR_READ_MPS_WIDTH` an arbitrary large line width will be accepted.

To use the free MPS format instead of the default MPS format the **MOSEK** parameter `MSK_IPAR_READ_MPS_FORMAT` should be changed.

10.3 The OPF Format

The *Optimization Problem Format (OPF)* is an alternative to LP and MPS files for specifying optimization problems. It is row-oriented, inspired by the CPLEX LP format.

Apart from containing objective, constraints, bounds etc. it may contain complete or partial solutions, comments and extra information relevant for solving the problem. It is designed to be easily read and modified by hand and to be forward compatible with possible future extensions.

Intended use

The OPF file format is meant to replace several other files:

- The LP file format: Any problem that can be written as an LP file can be written as an OPF file too; furthermore it naturally accommodates ranged constraints and variables as well as arbitrary characters in names, fixed expressions in the objective, empty constraints, and conic constraints.
- Parameter files: It is possible to specify integer, double and string parameters along with the problem (or in a separate OPF file).
- Solution files: It is possible to store a full or a partial solution in an OPF file and later reload it.

10.3.1 The File Format

The format uses tags to structure data. A simple example with the basic sections may look like this:

```
[comment]
This is a comment. You may write almost anything here...
[/comment]

# This is a single-line comment.

[objective min 'myobj']
x + 3 y + x^2 + 3 y^2 + z + 1
[/objective]

[constraints]
[con 'con01'] 4 <= x + y  [/con]
[/constraints]

[bounds]
[b] -10 <= x,y <= 10  [/b]

[cone quad] x,y,z  [/cone]
[/bounds]
```

A scope is opened by a tag of the form `[tag]` and closed by a tag of the form `[/tag]`. An opening tag may accept a list of unnamed and named arguments, for examples:

```
[tag value] tag with one unnamed argument [/tag]
[tag arg=value] tag with one named argument in quotes [/tag]
```

Unnamed arguments are identified by their order, while named arguments may appear in any order, but never before an unnamed argument. The `value` can be a quoted, single-quoted or double-quoted text string, i.e.

```
[tag 'value']      single-quoted value [/tag]
[tag arg='value']  single-quoted value [/tag]
[tag "value"]      double-quoted value [/tag]
[tag arg="value"]  double-quoted value [/tag]
```

Sections

The recognized tags are

[comment]

A comment section. This can contain *almost* any text: Between single quotes (') or double quotes (") any text may appear. Outside quotes the markup characters ([and]) must be prefixed by backslashes. Both single and double quotes may appear alone or inside a pair of quotes if it is prefixed by a backslash.

[objective]

The objective function: This accepts one or two parameters, where the first one (in the above example `min`) is either `min` or `max` (regardless of case) and defines the objective sense, and the second one (above `myobj`), if present, is the objective name. The section may contain linear and quadratic expressions. If several objectives are specified, all but the last are ignored.

[constraints]

This does not directly contain any data, but may contain the subsection `con` defining a linear constraint.

[`con`] defines a single constraint; if an argument is present ([`con NAME`]) this is used as the name of the constraint, otherwise it is given a null-name. The section contains a constraint definition written as linear and quadratic expressions with a lower bound, an upper bound, with both or with an equality. Examples:

```
[constraints]
[con 'con1'] 0 <= x + y      [/con]
[con 'con2'] 0 >= x + y      [/con]
[con 'con3'] 0 <= x + y <= 10 [/con]
[con 'con4']      x + y = 10 [/con]
[/constraints]
```

Constraint names are unique. If a constraint is specified which has the same name as a previously defined constraint, the new constraint replaces the existing one.

[bounds]

This does not directly contain any data, but may contain the subsections `b` (linear bounds on variables) and `cone` (quadratic cone).

[`b`]. Bound definition on one or several variables separated by comma (,). An upper or lower bound on a variable replaces any earlier defined bound on that variable. If only one bound (upper or lower) is given only this bound is replaced. This means that upper and lower bounds can be specified separately. So the OPF bound definition:

```
[b] x,y >= -10 [/b]
[b] x,y <= 10  [/b]
```

results in the bound $-10 \leq x, y \leq 10$.

[`cone`]. currently supports the *quadratic cone* and the *rotated quadratic cone*.

A conic constraint is defined as a set of variables which belong to a single unique cone.

- A quadratic cone of n variables x_1, \dots, x_n defines a constraint of the form

$$x_1^2 > \sum_{i=2}^n x_i^2.$$

- A rotated quadratic cone of n variables x_1, \dots, x_n defines a constraint of the form

$$x_1 x_2 > \sum_{i=3}^n x_i^2.$$

A `[bounds]`-section example:

```
[bounds]
[b]  0 <= x,y <= 10  [/b] # ranged bound
[b] 10 >= x,y >=  0  [/b] # ranged bound
[b]  0 <= x,y <= inf [/b] # using inf
[b]      x,y free    [/b] # free variables
# Let (x,y,z,w) belong to the cone K
[cone quad] x,y,z,w  [/cone] # quadratic cone
[cone rquad] x,y,z,w [/cone] # rotated quadratic cone
[/bounds]
```

By default all variables are free.

`[variables]`

This defines an ordering of variables as they should appear in the problem. This is simply a space-separated list of variable names.

`[integer]`

This contains a space-separated list of variables and defines the constraint that the listed variables must be integer values.

`[hints]`

This may contain only non-essential data; for example estimates of the number of variables, constraints and non-zeros. Placed before all other sections containing data this may reduce the time spent reading the file.

In the `hints` section, any subsection which is not recognized by **MOSEK** is simply ignored. In this section a hint in a subsection is defined as follows:

```
[hint ITEM] value [/hint]
```

where `ITEM` may be replaced by `numvar` (number of variables), `numcon` (number of linear/quadratic constraints), `numanz` (number of linear non-zeros in constraints) and `numqnz` (number of quadratic non-zeros in constraints).

`[solutions]`

This section can contain a set of full or partial solutions to a problem. Each solution must be specified using a `[solution]`-section, i.e.

```
[solutions]
[solution]...[/solution] #solution 1
[solution]...[/solution] #solution 2
#other solutions....
[solution]...[/solution] #solution n
[/solutions]
```

Note that a `[solution]`-section must be always specified inside a `[solutions]`-section. The syntax of a `[solution]`-section is the following:

```
[solution SOLTYPE status=STATUS]...[/solution]
```

where `SOLTYPE` is one of the strings

- `interior`, a non-basic solution,
- `basic`, a basic solution,
- `integer`, an integer solution,

and `STATUS` is one of the strings

- `UNKNOWN`,
- `OPTIMAL`,
- `INTEGER_OPTIMAL`,
- `PRIM_FEAS`,
- `DUAL_FEAS`,
- `PRIM_AND_DUAL_FEAS`,
- `NEAR_OPTIMAL`,
- `NEAR_PRIM_FEAS`,
- `NEAR_DUAL_FEAS`,
- `NEAR_PRIM_AND_DUAL_FEAS`,
- `PRIM_INFEAS_CER`,
- `DUAL_INFEAS_CER`,
- `NEAR_PRIM_INFEAS_CER`,
- `NEAR_DUAL_INFEAS_CER`,
- `NEAR_INTEGER_OPTIMAL`.

Most of these values are irrelevant for input solutions; when constructing a solution for simplex hot-start or an initial solution for a mixed integer problem the safe setting is `UNKNOWN`.

A `[solution]`-section contains `[con]` and `[var]` sections. Each `[con]` and `[var]` section defines solution information for a single variable or constraint, specified as list of `KEYWORD/value` pairs, in any order, written as

```
KEYWORD=value
```

Allowed keywords are as follows:

- `sk`. The status of the item, where the `value` is one of the following strings:
 - `LOW`, the item is on its lower bound.
 - `UPR`, the item is on its upper bound.
 - `FIX`, it is a fixed item.
 - `BAS`, the item is in the basis.

- SUPBAS, the item is super basic.
- UNK, the status is unknown.
- INF, the item is outside its bounds (infeasible).
- **lv1** Defines the level of the item.
- **s1** Defines the level of the dual variable associated with its lower bound.
- **su** Defines the level of the dual variable associated with its upper bound.
- **sn** Defines the level of the variable associated with its cone.
- **y** Defines the level of the corresponding dual variable (for constraints only).

A **[var]** section should always contain the items **sk**, **lv1**, **s1** and **su**. Items **s1** and **su** are not required for **integer** solutions.

A **[con]** section should always contain **sk**, **lv1**, **s1**, **su** and **y**.

An example of a solution section

```
[solution basic status=UNKNOWN]
[var x0] sk=LOW    lv1=5.0      [/var]
[var x1] sk=UPR    lv1=10.0     [/var]
[var x2] sk=SUPBAS lv1=2.0    s1=1.5 su=0.0 [/var]

[con c0] sk=LOW    lv1=3.0 y=0.0 [/con]
[con c0] sk=UPR    lv1=0.0 y=5.0 [/con]
[/solution]
```

- **[vendor]** This contains solver/vendor specific data. It accepts one argument, which is a vendor ID – for **MOSEK** the ID is simply **mosek** – and the section contains the subsection **parameters** defining solver parameters. When reading a vendor section, any unknown vendor can be safely ignored. This is described later.

Comments using the **#** may appear anywhere in the file. Between the **#** and the following line-break any text may be written, including markup characters.

Numbers

Numbers, when used for parameter values or coefficients, are written in the usual way by the **printf** function. That is, they may be prefixed by a sign (+ or -) and may contain an integer part, decimal part and an exponent. The decimal point is always **.** (a dot). Some examples are

```
1
1.0
.0
1.
1e10
1e+10
1e-10
```

Some *invalid* examples are

```
e10  # invalid, must contain either integer or decimal part
.     # invalid
.e10  # invalid
```

More formally, the following standard regular expression describes numbers as used:

```
[+|-]?([0-9]+[.][0-9]*|.[0-9]+)([eE][+|-]?[0-9]+)?
```

Names

Variable names, constraint names and objective name may contain arbitrary characters, which in some cases must be enclosed by quotes (single or double) that in turn must be preceded by a backslash. Unquoted names must begin with a letter (a-z or A-Z) and contain only the following characters: the letters a-z and A-Z, the digits 0-9, braces { and } and underscore (_).

Some examples of legal names:

```
an_unquoted_name
another_name{123}
'single quoted name'
"double quoted name"
"name with \"quote\" in it"
"name with []s in it"
```

10.3.2 Parameters Section

In the `vendor` section solver parameters are defined inside the `parameters` subsection. Each parameter is written as

```
[p PARAMETER_NAME] value [/p]
```

where `PARAMETER_NAME` is replaced by a **MOSEK** parameter name, usually of the form `MSK_IPAR_...`, `MSK_DPAR_...` or `MSK_SPAR_...`, and the `value` is replaced by the value of that parameter; both integer values and named values may be used. Some simple examples are

```
[vendor mosek]
[parameters]
[p MSK_IPAR_OPF_MAX_TERMS_PER_LINE] 10      [/p]
[p MSK_IPAR_OPF_WRITE_PARAMETERS]    MSK_ON [/p]
[p MSK_DPAR_DATA_TOL_BOUND_INF]      1.0e18 [/p]
[/parameters]
[/vendor]
```

10.3.3 Writing OPF Files from MOSEK

To write an OPF file set the parameter `MSK_IPAR_WRITE_DATA_FORMAT` to `MSK_DATA_FORMAT_OP` as this ensures that OPF format is used.

Then modify the following parameters to define what the file should contain:

<code>MSK_IPAR_OPF_WRITE_SOL_BAS</code>	Include basic solution, if defined.
<code>MSK_IPAR_OPF_WRITE_SOL_ITG</code>	Include integer solution, if defined.
<code>MSK_IPAR_OPF_WRITE_SOL_ITR</code>	Include interior solution, if defined.
<code>MSK_IPAR_OPF_WRITE_SOLUTIONS</code>	Include solutions if they are defined. If this is off, no solutions are included.
<code>MSK_IPAR_OPF_WRITE_HEADER</code>	Include a small header with comments.
<code>MSK_IPAR_OPF_WRITE_PROBLEM</code>	Include the problem itself — objective, constraints and bounds.
<code>MSK_IPAR_OPF_WRITE_PARAMETERS</code>	Include all parameter settings.
<code>MSK_IPAR_OPF_WRITE_HINTS</code>	Include hints about the size of the problem.

10.3.4 Examples

This section contains a set of small examples written in OPF and describing how to formulate linear, quadratic and conic problems.

Linear Example lo1.opf

Consider the example:

$$\begin{array}{llllll} \text{maximize} & 3x_0 & + & 1x_1 & + & 5x_2 & + & 1x_3 \\ \text{subject to} & 3x_0 & + & 1x_1 & + & 2x_2 & & = & 30, \\ & 2x_0 & + & 1x_1 & + & 3x_2 & + & 1x_3 & \geq & 15, \\ & & & 2x_1 & & & + & 3x_3 & \leq & 25, \end{array}$$

having the bounds

$$\begin{array}{lll} 0 & \leq & x_0 \leq \infty, \\ 0 & \leq & x_1 \leq 10, \\ 0 & \leq & x_2 \leq \infty, \\ 0 & \leq & x_3 \leq \infty. \end{array}$$

In the OPF format the example is displayed as shown in [Listing 10.1](#).

Listing 10.1: Example of an OPF file for a linear problem.

```
[comment]
  The lo1 example in OPF format
[/comment]

[hints]
  [hint NUMVAR] 4 [/hint]
  [hint NUMCON] 3 [/hint]
  [hint NUMANZ] 9 [/hint]
[/hints]

[variables disallow_new_variables]
  x1 x2 x3 x4
[/variables]

[objective maximize 'obj']
  3 x1 + x2 + 5 x3 + x4
[/objective]

[constraints]
  [con 'c1'] 3 x1 +   x2 + 2 x3           = 30 [/con]
  [con 'c2'] 2 x1 +   x2 + 3 x3 +   x4 >= 15 [/con]
  [con 'c3']      2 x2           + 3 x4 <= 25 [/con]
[/constraints]

[bounds]
  [b] 0 <= * [/b]
  [b] 0 <= x2 <= 10 [/b]
[/bounds]
```

Quadratic Example qo1.opf

An example of a quadratic optimization problem is

$$\begin{array}{ll} \text{minimize} & x_1^2 + 0.1x_2^2 + x_3^2 - x_1x_3 - x_2 \\ \text{subject to} & 1 \leq x_1 + x_2 + x_3, \\ & x \geq 0. \end{array}$$

This can be formulated in `opf` as shown below.

Listing 10.2: Example of an OPF file for a quadratic problem.

```
[comment]
  The qo1 example in OPF format
[/comment]

[hints]
  [hint NUMVAR] 3 [/hint]
  [hint NUMCON] 1 [/hint]
  [hint NUMANZ] 3 [/hint]
  [hint NUMQNZ] 4 [/hint]
[/hints]

[variables disallow_new_variables]
  x1 x2 x3
[/variables]

[objective minimize 'obj']
  # The quadratic terms are often written with a factor of 1/2 as here,
  # but this is not required.

  - x2 + 0.5 ( 2.0 x1 ^ 2 - 2.0 x3 * x1 + 0.2 x2 ^ 2 + 2.0 x3 ^ 2 )
[/objective]

[constraints]
  [con 'c1'] 1.0 <= x1 + x2 + x3 [/con]
[/constraints]

[bounds]
  [b] 0 <= * [/b]
[/bounds]
```

Conic Quadratic Example cqo1.opf

Consider the example:

$$\begin{aligned}
 &\text{minimize} && x_3 + x_4 + x_5 \\
 &\text{subject to} && x_0 + x_1 + 2x_2 = 1, \\
 & && x_0, x_1, x_2 \geq 0, \\
 & && x_3 \geq \sqrt{x_0^2 + x_1^2}, \\
 & && 2x_4x_5 \geq x_2^2.
 \end{aligned}$$

Please note that the type of the cones is defined by the parameter to `[cone ...]`; the content of the cone-section is the names of variables that belong to the cone. The resulting OPF file is in [Listing 10.3](#).

Listing 10.3: Example of an OPF file for a conic quadratic problem.

```
[comment]
  The cqo1 example in OPF format.
[/comment]

[hints]
  [hint NUMVAR] 6 [/hint]
  [hint NUMCON] 1 [/hint]
  [hint NUMANZ] 3 [/hint]
[/hints]

[variables disallow_new_variables]
  x1 x2 x3 x4 x5 x6
[/variables]
```

```

[objective minimize 'obj']
  x4 + x5 + x6
[/objective]

[constraints]
  [con 'c1']  x1 + x2 + 2e+00 x3 = 1e+00 [/con]
[/constraints]

[bounds]
  # We let all variables default to the positive orthant
  [b] 0 <= * [/b]

  # ...and change those that differ from the default
  [b] x4,x5,x6 free [/b]

  # Define quadratic cone:  $x_4 \geq \sqrt{x_1^2 + x_2^2}$ 
  [cone quad 'k1'] x4, x1, x2 [/cone]

  # Define rotated quadratic cone:  $2 x_5 x_6 \geq x_3^2$ 
  [cone rquad 'k2'] x5, x6, x3 [/cone]
[/bounds]

```

Mixed Integer Example `mil01.opf`

Consider the mixed integer problem:

$$\begin{aligned}
 &\text{maximize} && x_0 + 0.64x_1 \\
 &\text{subject to} && 50x_0 + 31x_1 \leq 250, \\
 & && 3x_0 - 2x_1 \geq -4, \\
 & && x_0, x_1 \geq 0 \quad \text{and integer}
 \end{aligned}$$

This can be implemented in OPF with the file in [Listing 10.4](#).

Listing 10.4: Example of an OPF file for a mixed-integer linear problem.

```

[comment]
  The mil01 example in OPF format
[/comment]

[hints]
  [hint NUMVAR] 2 [/hint]
  [hint NUMCON] 2 [/hint]
  [hint NUMANZ] 4 [/hint]
[/hints]

[variables disallow_new_variables]
  x1 x2
[/variables]

[objective maximize 'obj']
  x1 + 6.4e-1 x2
[/objective]

[constraints]
  [con 'c1'] 5e+1 x1 + 3.1e+1 x2 <= 2.5e+2 [/con]
  [con 'c2'] -4 <= 3 x1 - 2 x2 [/con]
[/constraints]

[bounds]
  [b] 0 <= * [/b]
[/bounds]

```

```
[integer]
  x1 x2
[/integer]
```

10.4 The CBF Format

This document constitutes the technical reference manual of the *Conic Benchmark Format* with file extension: `.cbf` or `.CBF`. It unifies linear, second-order cone (also known as conic quadratic) and semidefinite optimization with mixed-integer variables. The format has been designed with benchmark libraries in mind, and therefore focuses on compact and easily parsable representations. The problem structure is separated from the problem data, and the format moreover facilitates benchmarking of hotstart capability through sequences of changes.

10.4.1 How Instances Are Specified

This section defines the spectrum of conic optimization problems that can be formulated in terms of the keywords of the CBF format.

In the CBF format, conic optimization problems are considered in the following form:

$$\begin{aligned}
 & \min / \max && g^{obj} \\
 & \text{s.t.} && \begin{aligned} & g_i \in \mathcal{K}_i, && i \in \mathcal{I}, \\ & G_i \in \mathcal{K}_i, && i \in \mathcal{I}^{PSD}, \\ & x_j \in \mathcal{K}_j, && j \in \mathcal{J}, \\ & \bar{X}_j \in \mathcal{K}_j, && j \in \mathcal{J}^{PSD}. \end{aligned}
 \end{aligned} \tag{10.5}$$

- **Variables** are either scalar variables, x_j for $j \in \mathcal{J}$, or variables, \bar{X}_j for $j \in \mathcal{J}^{PSD}$. Scalar variables can also be declared as integer.
- **Constraints** are affine expressions of the variables, either scalar-valued g_i for $i \in \mathcal{I}$, or matrix-valued G_i for $i \in \mathcal{I}^{PSD}$

$$\begin{aligned}
 g_i &= \sum_{j \in \mathcal{J}^{PSD}} \langle F_{ij}, X_j \rangle + \sum_{j \in \mathcal{J}} a_{ij} x_j + b_i, \\
 G_i &= \sum_{j \in \mathcal{J}} x_j H_{ij} + D_i.
 \end{aligned}$$

- The **objective function** is a scalar-valued affine expression of the variables, either to be minimized or maximized. We refer to this expression as g^{obj}

$$g^{obj} = \sum_{j \in \mathcal{J}^{PSD}} \langle F_j^{obj}, X_j \rangle + \sum_{j \in \mathcal{J}} a_j^{obj} x_j + b^{obj}.$$

CBF format can represent the following cones \mathcal{K} :

- **Free domain** - A cone in the linear family defined by

$$\{x \in \mathbb{R}^n\}, \text{ for } n \geq 1.$$

- **Positive orthant** - A cone in the linear family defined by

$$\{x \in \mathbb{R}^n \mid x_j \geq 0 \text{ for } j = 1, \dots, n\}, \text{ for } n \geq 1.$$

- **Negative orthant** - A cone in the linear family defined by

$$\{x \in \mathbb{R}^n \mid x_j \leq 0 \text{ for } j = 1, \dots, n\}, \text{ for } n \geq 1.$$

- **Fixpoint zero** - A cone in the linear family defined by

$$\{x \in \mathbb{R}^n \mid x_j = 0 \text{ for } j = 1, \dots, n\}, \text{ for } n \geq 1.$$

- **Quadratic cone** - A cone in the second-order cone family defined by

$$\left\{ \begin{pmatrix} p \\ x \end{pmatrix} \in \mathbb{R} \times \mathbb{R}^{n-1}, p^2 \geq x^T x, p \geq 0 \right\}, \text{ for } n \geq 2.$$

- **Rotated quadratic cone** - A cone in the second-order cone family defined by

$$\left\{ \begin{pmatrix} p \\ q \\ x \end{pmatrix} \in \mathbb{R} \times \mathbb{R} \times \mathbb{R}^{n-2}, 2pq \geq x^T x, p \geq 0, q \geq 0 \right\}, \text{ for } n \geq 3.$$

10.4.2 The Structure of CBF Files

This section defines how information is written in the CBF format, without being specific about the type of information being communicated.

All information items belong to exactly one of the three groups of information. These information groups, and the order they must appear in, are:

1. File format.
2. Problem structure.
3. Problem data.

The first group, file format, provides information on how to interpret the file. The second group, problem structure, provides the information needed to deduce the type and size of the problem instance. Finally, the third group, problem data, specifies the coefficients and constants of the problem instance.

Information items

The format is composed as a list of information items. The first line of an information item is the **KEYWORD**, revealing the type of information provided. The second line - of some keywords only - is the **HEADER**, typically revealing the size of information that follows. The remaining lines are the **BODY** holding the actual information to be specified.

KEYWORD
BODY
KEYWORD
HEADER
BODY

The **KEYWORD** determines how each line in the **HEADER** and **BODY** is structured. Moreover, the number of lines in the **BODY** follows either from the **KEYWORD**, the **HEADER**, or from another information item required to precede it.

Embedded hotstart-sequences

A sequence of problem instances, based on the same problem structure, is within a single file. This is facilitated via the **CHANGE** within the problem data information group, as a separator between the information items of each instance. The information items following a **CHANGE** keyword are appending to, or changing (e.g., setting coefficients back to their default value of zero), the problem data of the preceding instance.

The sequence is intended for benchmarking of hotstart capability, where the solvers can reuse their internal state and solution (subject to the achieved accuracy) as warmpoint for the succeeding instance. Whenever this feature is unsupported or undesired, the keyword **CHANGE** should be interpreted as the end of file.

File encoding and line width restrictions

The format is based on the US-ASCII printable character set with two extensions as listed below. Note, by definition, that none of these extensions can be misinterpreted as printable US-ASCII characters:

- A line feed marks the end of a line, carriage returns are ignored.
- Comment-lines may contain unicode characters in UTF-8 encoding.

The line width is restricted to 512 bytes, with 3 bytes reserved for the potential carriage return, line feed and null-terminator.

Integers and floating point numbers must follow the ISO C decimal string representation in the standard C locale. The format does not impose restrictions on the magnitude of, or number of significant digits in numeric data, but the use of 64-bit integers and 64-bit IEEE 754 floating point numbers should be sufficient to avoid loss of precision.

Comment-line and whitespace rules

The format allows single-line comments respecting the following rule:

- Lines having first byte equal to '#' (US-ASCII 35) are comments, and should be ignored. Comments are only allowed between information items.

Given that a line is not a comment-line, whitespace characters should be handled according to the following rules:

- Leading and trailing whitespace characters should be ignored.
 - The separator between multiple pieces of information on one line, is either one or more whitespace characters.
- Lines containing only whitespace characters are empty, and should be ignored. Empty lines are only allowed between information items.

10.4.3 Problem Specification

The problem structure

The problem structure defines the objective sense, whether it is minimization and maximization. It also defines the index sets, \mathcal{J} , \mathcal{J}^{PSD} , \mathcal{I} and \mathcal{I}^{PSD} , which are all numbered from zero, $\{0, 1, \dots\}$, and empty until explicitly constructed.

- **Scalar variables** are constructed in vectors restricted to a conic domain, such as $(x_0, x_1) \in \mathbb{R}_+^2$, $(x_2, x_3, x_4) \in \mathcal{Q}^3$, etc. In terms of the Cartesian product, this generalizes to

$$x \in \mathcal{K}_1^{n_1} \times \mathcal{K}_2^{n_2} \times \dots \times \mathcal{K}_k^{n_k}$$

which in the CBF format becomes:

```
VAR
n k
K1 n1
K2 n2
...
Kk nk
```

where $\sum_i n_i = n$ is the total number of scalar variables. The list of supported cones is found in [Table 10.3](#). Integrality of scalar variables can be specified afterwards.

- **PSD variables** are constructed one-by-one. That is, $X_j \succeq \mathbf{0}^{n_j \times n_j}$ for $j \in \mathcal{J}^{PSD}$, constructs a matrix-valued variable of size $n_j \times n_j$ restricted to be symmetric positive semidefinite. In the CBF format, this list of constructions becomes:

```
PSDVAR
N
n1
n2
...
nN
```

where N is the total number of PSD variables.

- **Scalar constraints** are constructed in vectors restricted to a conic domain, such as $(g_0, g_1) \in \mathbb{R}_+^2$, $(g_2, g_3, g_4) \in \mathcal{Q}^3$, etc. In terms of the Cartesian product, this generalizes to

$$g \in \mathcal{K}_1^{m_1} \times \mathcal{K}_2^{m_2} \times \dots \times \mathcal{K}_k^{m_k}$$

which in the CBF format becomes:

```
CON
m k
K1 m1
K2 m2
..
Kk mk
```

where $\sum_i m_i = m$ is the total number of scalar constraints. The list of supported cones is found in [Table 10.3](#).

- **PSD constraints** are constructed one-by-one. That is, $G_i \succeq \mathbf{0}^{m_i \times m_i}$ for $i \in \mathcal{I}^{PSD}$, constructs a matrix-valued affine expressions of size $m_i \times m_i$ restricted to be symmetric positive semidefinite. In the CBF format, this list of constructions becomes

```
PSDCON
M
m1
m2
..
mM
```

where M is the total number of PSD constraints.

With the objective sense, variables (with integer indications) and constraints, the definitions of the many affine expressions follow in problem data.

Problem data

The problem data defines the coefficients and constants of the affine expressions of the problem instance. These are considered zero until explicitly defined, implying that instances with no keywords from this

information group are, in fact, valid. Duplicating or conflicting information is a failure to comply with the standard. Consequently, two coefficients written to the same position in a matrix (or to transposed positions in a symmetric matrix) is an error.

The affine expressions of the objective, g^{obj} , of the scalar constraints, g_i , and of the PSD constraints, G_i , are defined separately. The following notation uses the standard trace inner product for matrices, $\langle X, Y \rangle = \sum_{i,j} X_{ij}Y_{ij}$.

- The affine expression of the objective is defined as

$$g^{obj} = \sum_{j \in \mathcal{J}^{PSD}} \langle F_j^{obj}, X_j \rangle + \sum_{j \in \mathcal{J}} a_j^{obj} x_j + b^{obj},$$

in terms of the symmetric matrices, F_j^{obj} , and scalars, a_j^{obj} and b^{obj} .

- The affine expressions of the scalar constraints are defined, for $i \in \mathcal{I}$, as

$$g_i = \sum_{j \in \mathcal{J}^{PSD}} \langle F_{ij}, X_j \rangle + \sum_{j \in \mathcal{J}} a_{ij} x_j + b_i,$$

in terms of the symmetric matrices, F_{ij} , and scalars, a_{ij} and b_i .

- The affine expressions of the PSD constraints are defined, for $i \in \mathcal{I}^{PSD}$, as

$$G_i = \sum_{j \in \mathcal{J}} x_j H_{ij} + D_i,$$

in terms of the symmetric matrices, H_{ij} and D_i .

List of cones

The format uses an explicit syntax for symmetric positive semidefinite cones as shown above. For scalar variables and constraints, constructed in vectors, the supported conic domains and their minimum sizes are given as follows.

Table 10.3: Cones available in the CBF format

Name	CBF keyword	Cone family
Free domain	F	linear
Positive orthant	L+	linear
Negative orthant	L-	linear
Fixpoint zero	L=	linear
Quadratic cone	Q	second-order
Rotated quadratic cone	QR	second-order

10.4.4 File Format Keywords

VER

Description: The version of the Conic Benchmark Format used to write the file.

HEADER: None

BODY: One line formatted as:

INT

This is the version number.

Must appear exactly once in a file, as the first keyword.

OBJSENSE

Description: Define the objective sense.

HEADER: None

BODY: One line formatted as:

STR

having MIN indicates minimize, and MAX indicates maximize. Capital letters are required.

Must appear exactly once in a file.

PSDVAR

Description: Construct the PSD variables.

HEADER: One line formatted as:

INT

This is the number of PSD variables in the problem.

BODY: A list of lines formatted as:

INT

This indicates the number of rows (equal to the number of columns) in the matrix-valued PSD variable. The number of lines should match the number stated in the header.

VAR

Description: Construct the scalar variables.

HEADER: One line formatted as:

INT INT

This is the number of scalar variables, followed by the number of conic domains they are restricted to.

BODY: A list of lines formatted as:

STR INT

This indicates the cone name (see [Table 10.3](#)), and the number of scalar variables restricted to this cone. These numbers should add up to the number of scalar variables stated first in the header. The number of lines should match the second number stated in the header.

INT

Description: Declare integer requirements on a selected subset of scalar variables.

HEADER: one line formatted as:

INT

This is the number of integer scalar variables in the problem.

BODY: a list of lines formatted as:

INT

This indicates the scalar variable index $j \in \mathcal{J}$. The number of lines should match the number stated in the header.

Can only be used after the keyword **VAR**.

PSDCON

Description: Construct the PSD constraints.

HEADER: One line formatted as:

INT

This is the number of PSD constraints in the problem.

BODY: A list of lines formatted as:

INT

This indicates the number of rows (equal to the number of columns) in the matrix-valued affine expression of the PSD constraint. The number of lines should match the number stated in the header.

Can only be used after these keywords: **PSDVAR**, **VAR**.

CON

Description: Construct the scalar constraints.

HEADER: One line formatted as:

INT INT

This is the number of scalar constraints, followed by the number of conic domains they restrict to.

BODY: A list of lines formatted as:

STR INT

This indicates the cone name (see [Table 10.3](#)), and the number of affine expressions restricted to this cone. These numbers should add up to the number of scalar constraints stated first in the header. The number of lines should match the second number stated in the header.

Can only be used after these keywords: **PSDVAR**, **VAR**

OBJFCOORD

Description: Input sparse coordinates (quadruplets) to define the symmetric matrices F_j^{obj} , as used in the objective.

HEADER: One line formatted as:

INT

This is the number of coordinates to be specified.

BODY: A list of lines formatted as:

INT INT INT REAL

This indicates the PSD variable index $j \in \mathcal{J}^{PSD}$, the row index, the column index and the coefficient value. The number of lines should match the number stated in the header.

OBJACOORD

Description: Input sparse coordinates (pairs) to define the scalars, a_j^{obj} , as used in the objective.

HEADER: One line formatted as:

INT

This is the number of coordinates to be specified.

BODY: A list of lines formatted as:

INT REAL

This indicates the scalar variable index $j \in \mathcal{J}$ and the coefficient value. The number of lines should match the number stated in the header.

OBJBCOORD

Description: Input the scalar, b^{obj} , as used in the objective.

HEADER: None.

BODY: One line formatted as:

REAL

This indicates the coefficient value.

FCOORD

Description: Input sparse coordinates (quintuplets) to define the symmetric matrices, F_{ij} , as used in the scalar constraints.

HEADER: One line formatted as:

INT

This is the number of coordinates to be specified.

BODY: A list of lines formatted as:

INT INT INT INT REAL

This indicates the scalar constraint index $i \in \mathcal{I}$, the PSD variable index $j \in \mathcal{J}^{PSD}$, the row index, the column index and the coefficient value. The number of lines should match the number stated in the header.

ACOORD

Description: Input sparse coordinates (triplets) to define the scalars, a_{ij} , as used in the scalar constraints.

HEADER: One line formatted as:

INT

This is the number of coordinates to be specified.

BODY: A list of lines formatted as:

INT INT REAL

This indicates the scalar constraint index $i \in \mathcal{I}$, the scalar variable index $j \in \mathcal{J}$ and the coefficient value. The number of lines should match the number stated in the header.

BCOORD

Description: Input sparse coordinates (pairs) to define the scalars, b_i , as used in the scalar constraints.

HEADER: One line formatted as:

INT

This is the number of coordinates to be specified.

BODY: A list of lines formatted as:

INT REAL

This indicates the scalar constraint index $i \in \mathcal{I}$ and the coefficient value. The number of lines should match the number stated in the header.

HCOORD

Description: Input sparse coordinates (quintuplets) to define the symmetric matrices, H_{ij} , as used in the PSD constraints.

HEADER: One line formatted as:

INT

This is the number of coordinates to be specified.

BODY: A list of lines formatted as

INT INT INT INT REAL

This indicates the PSD constraint index $i \in \mathcal{I}^{PSD}$, the scalar variable index $j \in \mathcal{J}$, the row index, the column index and the coefficient value. The number of lines should match the number stated in the header.

DCOORD

Description: Input sparse coordinates (quadruplets) to define the symmetric matrices, D_i , as used in the PSD constraints.

HEADER: One line formatted as

INT

This is the number of coordinates to be specified.

BODY: A list of lines formatted as:

INT INT INT REAL

This indicates the PSD constraint index $i \in \mathcal{I}^{PSD}$, the row index, the column index and the coefficient value. The number of lines should match the number stated in the header.

CHANGE

Start of a new instance specification based on changes to the previous. Can be interpreted as the end of file when the hotstart-sequence is unsupported or undesired.

BODY: None

Header: None

10.4.5 CBF Format Examples

Minimal Working Example

The conic optimization problem (10.6), has three variables in a quadratic cone - first one is integer - and an affine expression in domain 0 (equality constraint).

$$\begin{aligned} & \text{minimize} && 5.1 x_0 \\ & \text{subject to} && 6.2 x_1 + 7.3 x_2 - 8.4 \in \{0\} \\ & && x \in \mathcal{Q}^3, x_0 \in \mathbb{Z}. \end{aligned} \tag{10.6}$$

Its formulation in the Conic Benchmark Format begins with the version of the CBF format used, to safeguard against later revisions.

```
VER
1
```

Next follows the problem structure, consisting of the objective sense, the number and domain of variables, the indices of integer variables, and the number and domain of scalar-valued affine expressions (i.e., the equality constraint).

```
OBJSENSE
MIN

VAR
3 1
Q 3

INT
1
0

CON
1 1
L= 1
```

Finally follows the problem data, consisting of the coefficients of the objective, the coefficients of the constraints, and the constant terms of the constraints. All data is specified on a sparse coordinate form.

```
OBJACOORD
1
0 5.1

ACOORD
2
0 1 6.2
0 2 7.3

BCOORD
1
0 -8.4
```

This concludes the example.

Mixing Linear, Second-order and Semidefinite Cones

The conic optimization problem (10.7), has a semidefinite cone, a quadratic cone over unordered subindices, and two equality constraints.

$$\begin{aligned}
 & \text{minimize} && \left\langle \begin{bmatrix} 2 & 1 & 0 \\ 1 & 2 & 1 \\ 0 & 1 & 2 \end{bmatrix}, X_1 \right\rangle + x_1 \\
 & \text{subject to} && \left\langle \begin{bmatrix} 1 & 0 & 0 \\ 0 & 1 & 0 \\ 0 & 0 & 1 \end{bmatrix}, X_1 \right\rangle + x_1 &= 1.0, \\
 & && \left\langle \begin{bmatrix} 1 & 1 & 1 \\ 1 & 1 & 1 \\ 1 & 1 & 1 \end{bmatrix}, X_1 \right\rangle + x_0 + x_2 &= 0.5, \\
 & && x_1 \geq \sqrt{x_0^2 + x_2^2}, \\
 & && X_1 \succeq \mathbf{0}.
 \end{aligned} \tag{10.7}$$

The equality constraints are easily rewritten to the conic form, $(g_0, g_1) \in \{0\}^2$, by moving constants such that the right-hand-side becomes zero. The quadratic cone does not fit under the `VAR` keyword in this variable permutation. Instead, it takes a scalar constraint $(g_2, g_3, g_4) = (x_1, x_0, x_2) \in \mathcal{Q}^3$, with scalar variables constructed as $(x_0, x_1, x_2) \in \mathbb{R}^3$. Its formulation in the CBF format is reported in the following list

```

# File written using this version of the Conic Benchmark Format:
#   | Version 1.
VER
1

# The sense of the objective is:
#   | Minimize.
OBJSENSE
MIN

# One PSD variable of this size:
#   | Three times three.
PSDVAR
1
3

# Three scalar variables in this one conic domain:
#   | Three are free.
VAR
3 1
F 3

# Five scalar constraints with affine expressions in two conic domains:
#   | Two are fixed to zero.
#   | Three are in conic quadratic domain.
CON
5 2
L= 2
Q 3

# Five coordinates in F^{obj}_j coefficients:
#   | F^{obj}[0][0,0] = 2.0
#   | F^{obj}[0][1,0] = 1.0
#   | and more...
OBJFCOORD
5
0 0 0 2.0
0 1 0 1.0
0 1 1 2.0

```



```

0 2 1 1.0
0 2 2 2.0

# One coordinate in a^{obj}_j coefficients:
#   | a^{obj}[1] = 1.0
OBJCOORD
1
1 1.0

# Nine coordinates in F_ij coefficients:
#   | F[0,0][0,0] = 1.0
#   | F[0,0][1,1] = 1.0
#   | and more...
FCOORD
9
0 0 0 0 1.0
0 0 1 1 1.0
0 0 2 2 1.0
1 0 0 0 1.0
1 0 1 0 1.0
1 0 2 0 1.0
1 0 1 1 1.0
1 0 2 1 1.0
1 0 2 2 1.0

# Six coordinates in a_ij coefficients:
#   | a[0,1] = 1.0
#   | a[1,0] = 1.0
#   | and more...
ACCOORD
6
0 1 1.0
1 0 1.0
1 2 1.0
2 1 1.0
3 0 1.0
4 2 1.0

# Two coordinates in b_i coefficients:
#   | b[0] = -1.0
#   | b[1] = -0.5
BCOORD
2
0 -1.0
1 -0.5

```

Mixing Semidefinite Variables and Linear Matrix Inequalities

The standard forms in semidefinite optimization are usually based either on semidefinite variables or linear matrix inequalities. In the CBF format, both forms are supported and can even be mixed as shown in.

$$\begin{aligned}
& \text{minimize} && \left\langle \begin{bmatrix} 1 & 0 \\ 0 & 1 \end{bmatrix}, X_1 \right\rangle + x_1 + x_2 + 1 \\
& \text{subject to} && \left\langle \begin{bmatrix} 0 & 1 \\ 1 & 0 \end{bmatrix}, X_1 \right\rangle - x_1 - x_2 \geq 0.0, \\
& && x_1 \begin{bmatrix} 0 & 1 \\ 1 & 3 \end{bmatrix} + x_2 \begin{bmatrix} 3 & 1 \\ 1 & 0 \end{bmatrix} - \begin{bmatrix} 1 & 0 \\ 0 & 1 \end{bmatrix} \succeq \mathbf{0}, \\
& && X_1 \succeq \mathbf{0}.
\end{aligned} \tag{10.8}$$

Its formulation in the CBF format is written in what follows

```
# File written using this version of the Conic Benchmark Format:
#       | Version 1.
VER
1

# The sense of the objective is:
#       | Minimize.
OBJSENSE
MIN

# One PSD variable of this size:
#       | Two times two.
PSDVAR
1
2

# Two scalar variables in this one conic domain:
#       | Two are free.
VAR
2 1
F 2

# One PSD constraint of this size:
#       | Two times two.
PSDCON
1
2

# One scalar constraint with an affine expression in this one conic domain:
#       | One is greater than or equal to zero.
CON
1 1
L+ 1

# Two coordinates in  $F^{\{obj\}}_j$  coefficients:
#       |  $F^{\{obj\}}[0][0,0] = 1.0$ 
#       |  $F^{\{obj\}}[0][1,1] = 1.0$ 
OBJFCOORD
2
0 0 0 1.0
0 1 1 1.0

# Two coordinates in  $a^{\{obj\}}_j$  coefficients:
#       |  $a^{\{obj\}}[0] = 1.0$ 
#       |  $a^{\{obj\}}[1] = 1.0$ 
OBJACOORD
2
0 1.0
1 1.0

# One coordinate in  $b^{\{obj\}}$  coefficient:
#       |  $b^{\{obj\}} = 1.0$ 
OBJBCOORD
1.0

# One coordinate in  $F_{ij}$  coefficients:
#       |  $F[0,0][1,0] = 1.0$ 
FCOORD
1
0 0 1 0 1.0

# Two coordinates in  $a_{ij}$  coefficients:
#       |  $a[0,0] = -1.0$ 
```

```
#      | a[0,1] = -1.0
ACCOORD
2
0 0 -1.0
0 1 -1.0

# Four coordinates in H_ij coefficients:
#      | H[0,0][1,0] = 1.0
#      | H[0,0][1,1] = 3.0
#      | and more...
HCOORD
4
0 0 1 0 1.0
0 0 1 1 3.0
0 1 0 0 3.0
0 1 1 0 1.0

# Two coordinates in D_i coefficients:
#      | D[0][0,0] = -1.0
#      | D[0][1,1] = -1.0
DCCOORD
2
0 0 0 -1.0
0 1 1 -1.0
```

Optimization Over a Sequence of Objectives

The linear optimization problem (10.9), is defined for a sequence of objectives such that hotstarting from one to the next might be advantages.

$$\begin{aligned}
 & \text{maximize}_k && g_k^{obj} \\
 & \text{subject to} && 50x_0 + 31 \leq 250, \\
 & && 3x_0 - 2x_1 \geq -4, \\
 & && x \in \mathbb{R}_+^2,
 \end{aligned} \tag{10.9}$$

given,

1. $g_0^{obj} = x_0 + 0.64x_1$.
2. $g_1^{obj} = 1.11x_0 + 0.76x_1$.
3. $g_2^{obj} = 1.11x_0 + 0.85x_1$.

Its formulation in the CBF format is reported in [Listing 10.5](#).

Listing 10.5: Problem (10.9) in CBF format.

```
# File written using this version of the Conic Benchmark Format:
#      | Version 1.
VER
1

# The sense of the objective is:
#      | Maximize.
OBJSENSE
MAX

# Two scalar variables in this one conic domain:
#      | Two are nonnegative.
VAR
2 1
L+ 2
```

```
# Two scalar constraints with affine expressions in these two conic domains:
#   | One is in the nonpositive domain.
#   | One is in the nonnegative domain.
CON
2 2
L- 1
L+ 1

# Two coordinates in a^{obj}_j coefficients:
#   | a^{obj}[0] = 1.0
#   | a^{obj}[1] = 0.64
OBJACCOORD
2
0 1.0
1 0.64

# Four coordinates in a_ij coefficients:
#   | a[0,0] = 50.0
#   | a[1,0] = 3.0
#   | and more...
ACCOORD
4
0 0 50.0
1 0 3.0
0 1 31.0
1 1 -2.0

# Two coordinates in b_i coefficients:
#   | b[0] = -250.0
#   | b[1] = 4.0
BCCOORD
2
0 -250.0
1 4.0

# New problem instance defined in terms of changes.
CHANGE

# Two coordinate changes in a^{obj}_j coefficients. Now it is:
#   | a^{obj}[0] = 1.11
#   | a^{obj}[1] = 0.76
OBJACCOORD
2
0 1.11
1 0.76

# New problem instance defined in terms of changes.
CHANGE

# One coordinate change in a^{obj}_j coefficients. Now it is:
#   | a^{obj}[0] = 1.11
#   | a^{obj}[1] = 0.85
OBJACCOORD
1
1 0.85
```

10.5 The XML (OSiL) Format

MOSEK can write data in the standard OSiL xml format. For a definition of the OSiL format please see <http://www.optimizationservices.org/>.

Only linear constraints (possibly with integer variables) are supported. By default output files with the extension `.xml` are written in the OSiL format.

The parameter `MSK_IPAR_WRITE_XML_MODE` controls if the linear coefficients in the A matrix are written in row or column order.

10.6 The Task Format

The Task format is **MOSEK**'s native binary format. It contains a complete image of a **MOSEK** task, i.e.

- Problem data: Linear, conic quadratic, semidefinite and quadratic data
- Problem item names: Variable names, constraints names, cone names etc.
- Parameter settings
- Solutions

There are a few things to be aware of:

- The task format *does not* support General Convex problems since these are defined by arbitrary user-defined functions.
- Status of a solution read from a file will *always* be unknown.

The format is based on the *TAR* (USTar) file format. This means that the individual pieces of data in a `.task` file can be examined by unpacking it as a *TAR* file. Please note that the inverse may not work: Creating a file using *TAR* will most probably not create a valid **MOSEK** Task file since the order of the entries is important.

10.7 The JSON Format

MOSEK provides the possibility to read/write problems in valid JSON format.

JSON (JavaScript Object Notation) is a lightweight data-interchange format. It is easy for humans to read and write. It is easy for machines to parse and generate. It is based on a subset of the JavaScript Programming Language, Standard ECMA-262 3rd Edition - December 1999. JSON is a text format that is completely language independent but uses conventions that are familiar to programmers of the C-family of languages, including C, C++, C#, Java, JavaScript, Perl, Python, and many others. These properties make JSON an ideal data-interchange language.

The official JSON website <http://www.json.org> provides plenty of information along with the format definition.

MOSEK defines two JSON-like formats:

- *jtask*
- *jsol*

Warning: Despite being text-based human-readable formats, *jtask* and *jsol* files will include no indentation and no new-lines, in order to keep the files as compact as possible. We therefore strongly advise to use JSON viewer tools to inspect *jtask* and *jsol* files.

10.7.1 *jtask* format

It stores a problem instance. The *jtask* format contains the same information as a *task format*.

Even though a *jtask* file is human-readable, we do not recommend users to create it by hand, but to rely on MOSEK.

10.7.2 *jsol* format

It stores a problem solution. The *jsol* format contains all solutions and information items.

10.7.3 A *jtask* example

In Listing 10.6 we present a file in the *jtask* format that corresponds to the sample problem from `lo1.lp`. The listing has been formatted for readability.

Listing 10.6: A formatted *jtask* file for the `lo1.lp` example.

```
{
  "$schema": "http://mosek.com/json/schema#",
  "Task/INFO": {
    "taskname": "lo1",
    "numvar": 4,
    "numcon": 3,
    "numcone": 0,
    "numbarvar": 0,
    "numanz": 9,
    "numsymmat": 0,
    "mosekver": [
      8,
      0,
      0,
      9
    ]
  },
  "Task/data": {
    "var": {
      "name": [
        "x1",
        "x2",
        "x3",
        "x4"
      ],
      "bk": [
        "lo",
        "ra",
        "lo",
        "lo"
      ],
      "b1": [
        0.0,
        0.0,
        0.0,
        0.0
      ],
      "bu": [
        1e+30,
        1e+1,
        1e+30,
        1e+30
      ]
    },
  },
}
```

```

    "type": [
        "cont",
        "cont",
        "cont",
        "cont"
    ]
},
"con": {
    "name": [
        "c1",
        "c2",
        "c3"
    ],
    "bk": [
        "fx",
        "lo",
        "up"
    ],
    "bl": [
        3e+1,
        1.5e+1,
        -1e+30
    ],
    "bu": [
        3e+1,
        1e+30,
        2.5e+1
    ]
},
"objective": {
    "sense": "max",
    "name": "obj",
    "c": {
        "subj": [
            0,
            1,
            2,
            3
        ],
        "val": [
            3e+0,
            1e+0,
            5e+0,
            1e+0
        ]
    },
    "cfix": 0.0
},
"A": {
    "subj": [
        0,
        0,
        0,
        1,
        1,
        1,
        1,
        1,
        2,
        2
    ],
    "subj": [
        0,
        1,

```

```

        2,
        0,
        1,
        2,
        3,
        1,
        3
    ],
    "val": [
        3e+0,
        1e+0,
        2e+0,
        2e+0,
        1e+0,
        3e+0,
        1e+0,
        2e+0,
        3e+0
    ]
}
},
"Task/parameters": {
    "iparam": {
        "ANA_SOL_BASIS": "ON",
        "ANA_SOL_PRINT_VIOLATED": "OFF",
        "AUTO_SORT_A_BEFORE_OPT": "OFF",
        "AUTO_UPDATE_SOL_INFO": "OFF",
        "BASIS_SOLVE_USE_PLUS_ONE": "OFF",
        "BI_CLEAN_OPTIMIZER": "OPTIMIZER_FREE",
        "BI_IGNORE_MAX_ITER": "OFF",
        "BI_IGNORE_NUM_ERROR": "OFF",
        "BI_MAX_ITERATIONS": 1000000,
        "CACHE_LICENSE": "ON",
        "CHECK_CONVEXITY": "CHECK_CONVEXITY_FULL",
        "COMPRESS_STATFILE": "ON",
        "CONCURRENT_NUM_OPTIMIZERS": 2,
        "CONCURRENT_PRIORITY_DUAL_SIMPLEX": 2,
        "CONCURRENT_PRIORITY_FREE_SIMPLEX": 3,
        "CONCURRENT_PRIORITY_INTPNT": 4,
        "CONCURRENT_PRIORITY_PRIMAL_SIMPLEX": 1,
        "FEASREPAIR_OPTIMIZE": "FEASREPAIR_OPTIMIZE_NONE",
        "INFEAS_GENERIC_NAMES": "OFF",
        "INFEAS_PREFER_PRIMAL": "ON",
        "INFEAS_REPORT_AUTO": "OFF",
        "INFEAS_REPORT_LEVEL": 1,
        "INTPNT_BASIS": "BI_ALWAYS",
        "INTPNT_DIFF_STEP": "ON",
        "INTPNT_FACTOR_DEBUG_LVL": 0,
        "INTPNT_FACTOR_METHOD": 0,
        "INTPNT_HOTSTART": "INTPNT_HOTSTART_NONE",
        "INTPNT_MAX_ITERATIONS": 400,
        "INTPNT_MAX_NUM_COR": -1,
        "INTPNT_MAX_NUM_REFINEMENT_STEPS": -1,
        "INTPNT_OFF_COL_TRH": 40,
        "INTPNT_ORDER_METHOD": "ORDER_METHOD_FREE",
        "INTPNT_REGULARIZATION_USE": "ON",
        "INTPNT_SCALING": "SCALING_FREE",
        "INTPNT_SOLVE_FORM": "SOLVE_FREE",
        "INTPNT_STARTING_POINT": "STARTING_POINT_FREE",
        "LIC_TRH_EXPIRY_WRN": 7,
        "LICENSE_DEBUG": "OFF",
        "LICENSE_PAUSE_TIME": 0,
        "LICENSE_SUPPRESS_EXPIRE_WRNS": "OFF",
    }
}

```



```

"LICENSE_WAIT": "OFF",
"LOG": 10,
"LOG_ANA_PRO": 1,
"LOG_BI": 4,
"LOG_BI_FREQ": 2500,
"LOG_CHECK_CONVEXITY": 0,
"LOG_CONCURRENT": 1,
"LOG_CUT_SECOND_OPT": 1,
"LOG_EXPAND": 0,
"LOG_FACTOR": 1,
"LOG_FEAS_REPAIR": 1,
"LOG_FILE": 1,
"LOG_HEAD": 1,
"LOG_INFEAS_ANA": 1,
"LOG_INTPNT": 4,
"LOG_MIO": 4,
"LOG_MIO_FREQ": 1000,
"LOG_OPTIMIZER": 1,
"LOG_ORDER": 1,
"LOG_PRESOLVE": 1,
"LOG_RESPONSE": 0,
"LOG_SENSITIVITY": 1,
"LOG_SENSITIVITY_OPT": 0,
"LOG_SIM": 4,
"LOG_SIM_FREQ": 1000,
"LOG_SIM_MINOR": 1,
"LOG_STORAGE": 1,
"MAX_NUM_WARNINGS": 10,
"MIO_BRANCH_DIR": "BRANCH_DIR_FREE",
"MIO_CONSTRUCT_SOL": "OFF",
"MIO_CUT_CLIQUE": "ON",
"MIO_CUT_CMIR": "ON",
"MIO_CUT_GMI": "ON",
"MIO_CUT_KNAPSACK_COVER": "OFF",
"MIO_HEURISTIC_LEVEL": -1,
"MIO_MAX_NUM_BRANCHES": -1,
"MIO_MAX_NUM_RELAXS": -1,
"MIO_MAX_NUM_SOLUTIONS": -1,
"MIO_MODE": "MIO_MODE_SATISFIED",
"MIO_MT_USER_CB": "ON",
"MIO_NODE_OPTIMIZER": "OPTIMIZER_FREE",
"MIO_NODE_SELECTION": "MIO_NODE_SELECTION_FREE",
"MIO_PERSPECTIVE_REFORMULATE": "ON",
"MIO_PROBING_LEVEL": -1,
"MIO_RINS_MAX_NODES": -1,
"MIO_ROOT_OPTIMIZER": "OPTIMIZER_FREE",
"MIO_ROOT_REPEAT_PRESOLVE_LEVEL": -1,
"MT_SPINCOUNT": 0,
"NUM_THREADS": 0,
"OPF_MAX_TERMS_PER_LINE": 5,
"OPF_WRITE_HEADER": "ON",
"OPF_WRITE_HINTS": "ON",
"OPF_WRITE_PARAMETERS": "OFF",
"OPF_WRITE_PROBLEM": "ON",
"OPF_WRITE_SOL_BAS": "ON",
"OPF_WRITE_SOL_ITG": "ON",
"OPF_WRITE_SOL_ITR": "ON",
"OPF_WRITE_SOLUTIONS": "OFF",
"OPTIMIZER": "OPTIMIZER_FREE",
"PARAM_READ_CASE_NAME": "ON",
"PARAM_READ_IGN_ERROR": "OFF",
"PRESOLVE_ELIMINATOR_MAX_FILL": -1,
"PRESOLVE_ELIMINATOR_MAX_NUM_TRIES": -1,

```

```

"PRESOLVE_LEVEL":-1,
"PRESOLVE_LINDEP_ABS_WORK_TRH":100,
"PRESOLVE_LINDEP_REL_WORK_TRH":100,
"PRESOLVE_LINDEP_USE":"ON",
"PRESOLVE_MAX_NUM_REDUCTIONS":-1,
"PRESOLVE_USE":"PRESOLVE_MODE_FREE",
"PRIMAL_REPAIR_OPTIMIZER":"OPTIMIZER_FREE",
"QO_SEPARABLE_REFORMULATION":"OFF",
"READ_DATA_COMPRESSED":"COMPRESS_FREE",
"READ_DATA_FORMAT":"DATA_FORMAT_EXTENSION",
"READ_DEBUG":"OFF",
"READ_KEEP_FREE_CON":"OFF",
"READ_LP_DROP_NEW_VARS_IN_BOU":"OFF",
"READ_LP_QUOTED_NAMES":"ON",
"READ_MPS_FORMAT":"MPS_FORMAT_FREE",
"READ_MPS_WIDTH":1024,
"READ_TASK_IGNORE_PARAM":"OFF",
"SENSITIVITY_ALL":"OFF",
"SENSITIVITY_OPTIMIZER":"OPTIMIZER_FREE_SIMPLEX",
"SENSITIVITY_TYPE":"SENSITIVITY_TYPE_BASIS",
"SIM_BASIS_FACTOR_USE":"ON",
"SIM_DEGEN":"SIM_DEGEN_FREE",
"SIM_DUAL_CRASH":90,
"SIM_DUAL_PHASEONE_METHOD":0,
"SIM_DUAL_RESTRICT_SELECTION":50,
"SIM_DUAL_SELECTION":"SIM_SELECTION_FREE",
"SIM_EXPLOIT_DUPVEC":"SIM_EXPLOIT_DUPVEC_OFF",
"SIM_HOTSTART":"SIM_HOTSTART_FREE",
"SIM_HOTSTART_LU":"ON",
"SIM_INTEGER":0,
"SIM_MAX_ITERATIONS":10000000,
"SIM_MAX_NUM_SETBACKS":250,
"SIM_NON_SINGULAR":"ON",
"SIM_PRIMAL_CRASH":90,
"SIM_PRIMAL_PHASEONE_METHOD":0,
"SIM_PRIMAL_RESTRICT_SELECTION":50,
"SIM_PRIMAL_SELECTION":"SIM_SELECTION_FREE",
"SIM_REFACTOR_FREQ":0,
"SIM_REFORMULATION":"SIM_REFORMULATION_OFF",
"SIM_SAVE_LU":"OFF",
"SIM_SCALING":"SCALING_FREE",
"SIM_SCALING_METHOD":"SCALING_METHOD_POW2",
"SIM_SOLVE_FORM":"SOLVE_FREE",
"SIM_STABILITY_PRIORITY":50,
"SIM_SWITCH_OPTIMIZER":"OFF",
"SOL_FILTER_KEEP_BASIC":"OFF",
"SOL_FILTER_KEEP_RANGED":"OFF",
"SOL_READ_NAME_WIDTH":-1,
"SOL_READ_WIDTH":1024,
"SOLUTION_CALLBACK":"OFF",
"TIMING_LEVEL":1,
"WRITE_BAS_CONSTRAINTS":"ON",
"WRITE_BAS_HEAD":"ON",
"WRITE_BAS_VARIABLES":"ON",
"WRITE_DATA_COMPRESSED":0,
"WRITE_DATA_FORMAT":"DATA_FORMAT_EXTENSION",
"WRITE_DATA_PARAM":"OFF",
"WRITE_FREE_CON":"OFF",
"WRITE_GENERIC_NAMES":"OFF",
"WRITE_GENERIC_NAMES_IO":1,
"WRITE_IGNORE_INCOMPATIBLE_CONIC_ITEMS":"OFF",
"WRITE_IGNORE_INCOMPATIBLE_ITEMS":"OFF",
"WRITE_IGNORE_INCOMPATIBLE_NL_ITEMS":"OFF",

```

```

    "WRITE_IGNORE_INCOMPATIBLE_PSD_ITEMS": "OFF",
    "WRITE_INT_CONSTRAINTS": "ON",
    "WRITE_INT_HEAD": "ON",
    "WRITE_INT_VARIABLES": "ON",
    "WRITE_LP_FULL_OBJ": "ON",
    "WRITE_LP_LINE_WIDTH": 80,
    "WRITE_LP_QUOTED_NAMES": "ON",
    "WRITE_LP_STRICT_FORMAT": "OFF",
    "WRITE_LP_TERMS_PER_LINE": 10,
    "WRITE_MPS_FORMAT": "MPS_FORMAT_FREE",
    "WRITE_MPS_INT": "ON",
    "WRITE_PRECISION": 15,
    "WRITE_SOL_BARVARIABLES": "ON",
    "WRITE_SOL_CONSTRAINTS": "ON",
    "WRITE_SOL_HEAD": "ON",
    "WRITE_SOL_IGNORE_INVALID_NAMES": "OFF",
    "WRITE_SOL_VARIABLES": "ON",
    "WRITE_TASK_INC_SOL": "ON",
    "WRITE_XML_MODE": "WRITE_XML_MODE_ROW"
  },
  "dparam": {
    "ANA_SOL_INFEAS_TOL": 1e-6,
    "BASIS_REL_TOL_S": 1e-12,
    "BASIS_TOL_S": 1e-6,
    "BASIS_TOL_X": 1e-6,
    "CHECK_CONVEXITY_REL_TOL": 1e-10,
    "DATA_TOL_AIJ": 1e-12,
    "DATA_TOL_AIJ_HUGE": 1e+20,
    "DATA_TOL_AIJ_LARGE": 1e+10,
    "DATA_TOL_BOUND_INF": 1e+16,
    "DATA_TOL_BOUND_WRN": 1e+8,
    "DATA_TOL_C_HUGE": 1e+16,
    "DATA_TOL_CJ_LARGE": 1e+8,
    "DATA_TOL_QIJ": 1e-16,
    "DATA_TOL_X": 1e-8,
    "FEASREPAIR_TOL": 1e-10,
    "INTPNT_CO_TOL_DFEAS": 1e-8,
    "INTPNT_CO_TOL_INFEAS": 1e-10,
    "INTPNT_CO_TOL_MU_RED": 1e-8,
    "INTPNT_CO_TOL_NEAR_REL": 1e+3,
    "INTPNT_CO_TOL_PFEAS": 1e-8,
    "INTPNT_CO_TOL_REL_GAP": 1e-7,
    "INTPNT_NL_MERIT_BAL": 1e-4,
    "INTPNT_NL_TOL_DFEAS": 1e-8,
    "INTPNT_NL_TOL_MU_RED": 1e-12,
    "INTPNT_NL_TOL_NEAR_REL": 1e+3,
    "INTPNT_NL_TOL_PFEAS": 1e-8,
    "INTPNT_NL_TOL_REL_GAP": 1e-6,
    "INTPNT_NL_TOL_REL_STEP": 9.95e-1,
    "INTPNT_QO_TOL_DFEAS": 1e-8,
    "INTPNT_QO_TOL_INFEAS": 1e-10,
    "INTPNT_QO_TOL_MU_RED": 1e-8,
    "INTPNT_QO_TOL_NEAR_REL": 1e+3,
    "INTPNT_QO_TOL_PFEAS": 1e-8,
    "INTPNT_QO_TOL_REL_GAP": 1e-8,
    "INTPNT_TOL_DFEAS": 1e-8,
    "INTPNT_TOL_DSAFE": 1e+0,
    "INTPNT_TOL_INFEAS": 1e-10,
    "INTPNT_TOL_MU_RED": 1e-16,
    "INTPNT_TOL_PATH": 1e-8,
    "INTPNT_TOL_PFEAS": 1e-8,
    "INTPNT_TOL_PSAFE": 1e+0,
    "INTPNT_TOL_REL_GAP": 1e-8,

```

```

    "INTPNT_TOL_REL_STEP":9.999e-1,
    "INTPNT_TOL_STEP_SIZE":1e-6,
    "LOWER_OBJ_CUT":-1e+30,
    "LOWER_OBJ_CUT_FINITE_TRH":-5e+29,
    "MIO_DISABLE_TERM_TIME":-1e+0,
    "MIO_MAX_TIME":-1e+0,
    "MIO_MAX_TIME_APRX_OPT":6e+1,
    "MIO_NEAR_TOL_ABS_GAP":0.0,
    "MIO_NEAR_TOL_REL_GAP":1e-3,
    "MIO_REL_GAP_CONST":1e-10,
    "MIO_TOL_ABS_GAP":0.0,
    "MIO_TOL_ABS_RELAX_INT":1e-5,
    "MIO_TOL_FEAS":1e-6,
    "MIO_TOL_REL_DUAL_BOUND_IMPROVEMENT":0.0,
    "MIO_TOL_REL_GAP":1e-4,
    "MIO_TOL_X":1e-6,
    "OPTIMIZER_MAX_TIME":-1e+0,
    "PRESOLVE_TOL_ABS_LINDEP":1e-6,
    "PRESOLVE_TOL_AIJ":1e-12,
    "PRESOLVE_TOL_REL_LINDEP":1e-10,
    "PRESOLVE_TOL_S":1e-8,
    "PRESOLVE_TOL_X":1e-8,
    "QCQO_REFORMULATE_REL_DROP_TOL":1e-15,
    "SEMIDEFINITE_TOL_APPROX":1e-10,
    "SIM_LU_TOL_REL_PIV":1e-2,
    "SIMPLEX_ABS_TOL_PIV":1e-7,
    "UPPER_OBJ_CUT":1e+30,
    "UPPER_OBJ_CUT_FINITE_TRH":5e+29
  },
  "sparam":{
    "BAS_SOL_FILE_NAME":"",
    "DATA_FILE_NAME":"examples/tools/data/lo1.mps",
    "DEBUG_FILE_NAME":"",
    "INT_SOL_FILE_NAME":"",
    "ITR_SOL_FILE_NAME":"",
    "MIO_DEBUG_STRING":"",
    "PARAM_COMMENT_SIGN":"%%",
    "PARAM_READ_FILE_NAME":"",
    "PARAM_WRITE_FILE_NAME":"",
    "READ_MPS_BOU_NAME":"",
    "READ_MPS_OBJ_NAME":"",
    "READ_MPS_RAN_NAME":"",
    "READ_MPS_RHS_NAME":"",
    "SENSITIVITY_FILE_NAME":"",
    "SENSITIVITY_RES_FILE_NAME":"",
    "SOL_FILTER_XC_LOW":"",
    "SOL_FILTER_XC_UPR":"",
    "SOL_FILTER_XX_LOW":"",
    "SOL_FILTER_XX_UPR":"",
    "STAT_FILE_NAME":"",
    "STAT_KEY":"",
    "STAT_NAME":"",
    "WRITE_LP_GEN_VAR_NAME":"XMSKGEN"
  }
}

```

10.8 The Solution File Format

MOSEK provides several solution files depending on the problem type and the optimizer used:

- *basis solution file* (extension `.bas`) if the problem is optimized using the simplex optimizer or basis identification is performed,
- *interior solution file* (extension `.sol`) if a problem is optimized using the interior-point optimizer and no basis identification is required,
- *integer solution file* (extension `.int`) if the problem contains integer constrained variables.

All solution files have the format:

NAME	:	<problem name>						
PROBLEM STATUS	:	<status of the problem>						
SOLUTION STATUS	:	<status of the solution>						
OBJECTIVE NAME	:	<name of the objective function>						
PRIMAL OBJECTIVE	:	<primal objective value corresponding to the solution>						
DUAL OBJECTIVE	:	<dual objective value corresponding to the solution>						
CONSTRAINTS								
INDEX	NAME	AT	ACTIVITY	LOWER LIMIT	UPPER LIMIT	DUAL LOWER	DUAL UPPER	
?	<name>	??	<a value>	<a value>	<a value>	<a value>	<a value>	
VARIABLES								
INDEX	NAME	AT	ACTIVITY	LOWER LIMIT	UPPER LIMIT	DUAL LOWER	DUAL UPPER	CONIC
↪DUAL								
?	<name>	??	<a value>	<a value>	<a value>	<a value>	<a value>	<a value>

In the example the fields ? and <> will be filled with problem and solution specific information. As can be observed a solution report consists of three sections, i.e.

- **HEADER** In this section, first the name of the problem is listed and afterwards the problem and solution status are shown. Next the primal and dual objective values are displayed.
- **CONSTRAINTS** For each constraint i of the form

$$l_i^c \leq \sum_{j=1}^n a_{ij}x_j \leq u_i^c, \quad (10.10)$$

the following information is listed:

- **INDEX**: A sequential index assigned to the constraint by **MOSEK**
- **NAME**: The name of the constraint assigned by the user.
- **AT**: The status of the constraint. In Table 10.4 the possible values of the status keys and their interpretation are shown.

Table 10.4: Status keys.

Status key	Interpretation
UN	Unknown status
BS	Is basic
SB	Is superbasic
LL	Is at the lower limit (bound)
UL	Is at the upper limit (bound)
EQ	Lower limit is identical to upper limit
**	Is infeasible i.e. the lower limit is greater than the upper limit.

- **ACTIVITY**: the quantity $\sum_{j=1}^n a_{ij}x_j^*$, where x^* is the value of the primal solution.
- **LOWER LIMIT**: the quantity l_i^c (see (10.10).)
- **UPPER LIMIT**: the quantity u_i^c (see (10.10).)
- **DUAL LOWER**: the dual multiplier corresponding to the lower limit on the constraint.
- **DUAL UPPER**: the dual multiplier corresponding to the upper limit on the constraint.

- **VARIABLES** The last section of the solution report lists information about the variables. This information has a similar interpretation as for the constraints. However, the column with the header CONIC DUAL is included for problems having one or more conic constraints. This column shows the dual variables corresponding to the conic constraints.

Example: lo1.sol

In Listing 10.7 we show the solution file for the lo1.opf problem.

Listing 10.7: An example of .sol file.

NAME	:				
PROBLEM STATUS	:	PRIMAL_AND_DUAL_FEASIBLE			
SOLUTION STATUS	:	OPTIMAL			
OBJECTIVE NAME	:	obj			
PRIMAL OBJECTIVE	:	8.3333333e+01			
DUAL OBJECTIVE	:	8.3333333e+01			
CONSTRAINTS					
INDEX	NAME	AT ACTIVITY	LOWER LIMIT	UPPER LIMIT	
	→DUAL LOWER	DUAL UPPER			
0	c1	EQ 3.0000000000000e+01	3.00000000e+01	3.00000000e+01	-0.
	→0000000000000e+00	-2.4999999741654e+00			
1	c2	SB 5.3333333049188e+01	1.50000000e+01	NONE	2.
	→09157603759397e-10	-0.0000000000000e+00			
2	c3	UL 2.4999999842049e+01	NONE	2.50000000e+01	-0.
	→0000000000000e+00	-3.33333332895110e-01			
VARIABLES					
INDEX	NAME	AT ACTIVITY	LOWER LIMIT	UPPER LIMIT	
	→DUAL LOWER	DUAL UPPER			
0	x1	LL 1.67020427073508e-09	0.00000000e+00	NONE	-4.
	→49999999528055e+00	-0.0000000000000e+00			
1	x2	LL 2.93510446280504e-09	0.00000000e+00	1.00000000e+01	-2.
	→16666666494916e+00	6.20863861687316e-10			
2	x3	SB 1.4999999899425e+01	0.00000000e+00	NONE	-8.
	→79123177454657e-10	-0.0000000000000e+00			
3	x4	SB 8.33333332273116e+00	0.00000000e+00	NONE	-1.
	→69795978899185e-09	-0.0000000000000e+00			

BIBLIOGRAPHY

- [Naz87] J. L. Nazareth. *Computer Solution of Linear Programs*. Oxford University Press, New York, 1987.

Enumerations

MSKaccmodee, 99
 MSK_ACC_CON, 99
 MSK_ACC_VAR, 99
 MSKbasindtypee, 99
 MSK_BI_ALWAYS, 100
 MSK_BI_IF_FEASIBLE, 100
 MSK_BI_NEVER, 99
 MSK_BI_NO_ERROR, 100
 MSK_BI_RESERVED, 100
 MSKboundkeye, 100
 MSK_BK_FR, 100
 MSK_BK_FX, 100
 MSK_BK_LO, 100
 MSK_BK_RA, 100
 MSK_BK_UP, 100
 MSKbranchdire, 117
 MSK_BRANCH_DIR_DOWN, 117
 MSK_BRANCH_DIR_FAR, 117
 MSK_BRANCH_DIR_FREE, 117
 MSK_BRANCH_DIR_GUIDED, 117
 MSK_BRANCH_DIR_NEAR, 117
 MSK_BRANCH_DIR_PSEUDOCOST, 118
 MSK_BRANCH_DIR_ROOT_LP, 117
 MSK_BRANCH_DIR_UP, 117
 MSKcallbackcodee, 101
 MSK_CALLBACK_BEGIN_BI, 102
 MSK_CALLBACK_BEGIN_CONIC, 102
 MSK_CALLBACK_BEGIN_DUAL_BI, 103
 MSK_CALLBACK_BEGIN_DUAL_SENSITIVITY, 105
 MSK_CALLBACK_BEGIN_DUAL_SETUP_BI, 105
 MSK_CALLBACK_BEGIN_DUAL_SIMPLEX, 104
 MSK_CALLBACK_BEGIN_DUAL_SIMPLEX_BI, 104
 MSK_CALLBACK_BEGIN_FULL_CONVEXITY_CHECK, 106
 MSK_CALLBACK_BEGIN_INFEAS_ANA, 105
 MSK_CALLBACK_BEGIN_INTPNT, 102
 MSK_CALLBACK_BEGIN_LICENSE_WAIT, 105
 MSK_CALLBACK_BEGIN_MIO, 104
 MSK_CALLBACK_BEGIN_OPTIMIZER, 102
 MSK_CALLBACK_BEGIN_PRESOLVE, 102
 MSK_CALLBACK_BEGIN_PRIMAL_BI, 103
 MSK_CALLBACK_BEGIN_PRIMAL_DUAL_SIMPLEX, 104
 MSK_CALLBACK_BEGIN_PRIMAL_DUAL_SIMPLEX_BI, 103
 MSK_CALLBACK_BEGIN_PRIMAL_REPAIR, 106
 MSK_CALLBACK_BEGIN_PRIMAL_SENSITIVITY, 105
 MSK_CALLBACK_BEGIN_PRIMAL_SETUP_BI, 105
 MSK_CALLBACK_BEGIN_PRIMAL_SIMPLEX, 104
 MSK_CALLBACK_BEGIN_PRIMAL_SIMPLEX_BI, 103
 MSK_CALLBACK_BEGIN_QCQO_REFORMULATE, 105
 MSK_CALLBACK_BEGIN_READ, 106
 MSK_CALLBACK_BEGIN_ROOT_CUTGEN, 101
 MSK_CALLBACK_BEGIN_SIMPLEX, 104
 MSK_CALLBACK_BEGIN_SIMPLEX_BI, 103
 MSK_CALLBACK_BEGIN_TO_CONIC, 106
 MSK_CALLBACK_BEGIN_WRITE, 106
 MSK_CALLBACK_CONIC, 102
 MSK_CALLBACK_DUAL_SIMPLEX, 102
 MSK_CALLBACK_END_BI, 102
 MSK_CALLBACK_END_CONIC, 102
 MSK_CALLBACK_END_DUAL_BI, 103
 MSK_CALLBACK_END_DUAL_SENSITIVITY, 105
 MSK_CALLBACK_END_DUAL_SETUP_BI, 105
 MSK_CALLBACK_END_DUAL_SIMPLEX, 104
 MSK_CALLBACK_END_DUAL_SIMPLEX_BI, 104
 MSK_CALLBACK_END_FULL_CONVEXITY_CHECK, 106
 MSK_CALLBACK_END_INFEAS_ANA, 105
 MSK_CALLBACK_END_INTPNT, 102
 MSK_CALLBACK_END_LICENSE_WAIT, 105
 MSK_CALLBACK_END_MIO, 104
 MSK_CALLBACK_END_OPTIMIZER, 102
 MSK_CALLBACK_END_PRESOLVE, 102
 MSK_CALLBACK_END_PRIMAL_BI, 103
 MSK_CALLBACK_END_PRIMAL_DUAL_SIMPLEX, 105
 MSK_CALLBACK_END_PRIMAL_DUAL_SIMPLEX_BI, 103
 MSK_CALLBACK_END_PRIMAL_REPAIR, 106
 MSK_CALLBACK_END_PRIMAL_SENSITIVITY, 105
 MSK_CALLBACK_END_PRIMAL_SETUP_BI, 105
 MSK_CALLBACK_END_PRIMAL_SIMPLEX, 104
 MSK_CALLBACK_END_PRIMAL_SIMPLEX_BI, 103
 MSK_CALLBACK_END_QCQO_REFORMULATE, 105
 MSK_CALLBACK_END_READ, 106
 MSK_CALLBACK_END_ROOT_CUTGEN, 102
 MSK_CALLBACK_END_SIMPLEX, 105
 MSK_CALLBACK_END_SIMPLEX_BI, 104
 MSK_CALLBACK_END_TO_CONIC, 106
 MSK_CALLBACK_END_WRITE, 106
 MSK_CALLBACK_IM_BI, 102
 MSK_CALLBACK_IM_CONIC, 102
 MSK_CALLBACK_IM_DUAL_BI, 103
 MSK_CALLBACK_IM_DUAL_SENSITIVITY, 105

MSK_CALLBACK_IM_DUAL_SIMPLEX, 104
MSK_CALLBACK_IM_FULL_CONVEXITY_CHECK, 106
MSK_CALLBACK_IM_INTPNT, 102
MSK_CALLBACK_IM_LICENSE_WAIT, 105
MSK_CALLBACK_IM_LU, 106
MSK_CALLBACK_IM_MIO, 104
MSK_CALLBACK_IM_MIO_DUAL_SIMPLEX, 105
MSK_CALLBACK_IM_MIO_INTPNT, 105
MSK_CALLBACK_IM_MIO_PRIMAL_SIMPLEX, 105
MSK_CALLBACK_IM_ORDER, 106
MSK_CALLBACK_IM PRESOLVE, 102
MSK_CALLBACK_IM_PRIMAL_BI, 103
MSK_CALLBACK_IM_PRIMAL_DUAL_SIMPLEX, 104
MSK_CALLBACK_IM_PRIMAL_SENSIVITY, 105
MSK_CALLBACK_IM_PRIMAL_SIMPLEX, 104
MSK_CALLBACK_IM_QO_REFORMULATE, 106
MSK_CALLBACK_IM_READ, 106
MSK_CALLBACK_IM_ROOT_CUTGEN, 102
MSK_CALLBACK_IM_SIMPLEX, 106
MSK_CALLBACK_IM_SIMPLEX_BI, 103
MSK_CALLBACK_INTPNT, 102
MSK_CALLBACK_NEW_INT_MIO, 104
MSK_CALLBACK_PRIMAL_SIMPLEX, 102
MSK_CALLBACK_READ_OPF, 106
MSK_CALLBACK_READ_OPF_SECTION, 106
MSK_CALLBACK_SOLVING_REMOTE, 106
MSK_CALLBACK_UPDATE_DUAL_BI, 103
MSK_CALLBACK_UPDATE_DUAL_SIMPLEX, 104
MSK_CALLBACK_UPDATE_DUAL_SIMPLEX_BI, 104
MSK_CALLBACK_UPDATE_PRESOLVE, 102
MSK_CALLBACK_UPDATE_PRIMAL_BI, 103
MSK_CALLBACK_UPDATE_PRIMAL_DUAL_SIMPLEX,
104
MSK_CALLBACK_UPDATE_PRIMAL_DUAL_SIMPLEX_BI,
103
MSK_CALLBACK_UPDATE_PRIMAL_SIMPLEX, 104
MSK_CALLBACK_UPDATE_PRIMAL_SIMPLEX_BI, 103
MSK_CALLBACK_WRITE_OPF, 106
MSKcheckconvexitytypee, 106
MSK_CHECK_CONVEXITY_FULL, 107
MSK_CHECK_CONVEXITY_NONE, 106
MSK_CHECK_CONVEXITY_SIMPLE, 107
MSKcompresstypee, 107
MSK_COMPRESS_FREE, 107
MSK_COMPRESS_GZIP, 107
MSK_COMPRESS_NONE, 107
MSKconetypee, 107
MSK_CT_QUAD, 107
MSK_CT_RQUAD, 107
MSKdataformate, 107
MSK_DATA_FORMAT_CB, 108
MSK_DATA_FORMAT_EXTENSION, 107
MSK_DATA_FORMAT_FREE_MPS, 107
MSK_DATA_FORMAT_JSON_TASK, 108
MSK_DATA_FORMAT_LP, 107
MSK_DATA_FORMAT_MPS, 107
MSK_DATA_FORMAT_OP, 107
MSK_DATA_FORMAT_TASK, 107
MSK_DATA_FORMAT_XML, 107
MSKdinfiteme, 108
MSK_DINF_BI_CLEAN_DUAL_TIME, 108
MSK_DINF_BI_CLEAN_PRIMAL_DUAL_TIME, 108
MSK_DINF_BI_CLEAN_PRIMAL_TIME, 108
MSK_DINF_BI_CLEAN_TIME, 108
MSK_DINF_BI_DUAL_TIME, 108
MSK_DINF_BI_PRIMAL_TIME, 108
MSK_DINF_BI_TIME, 108
MSK_DINF_INTPNT_DUAL_FEAS, 108
MSK_DINF_INTPNT_DUAL_OBJ, 108
MSK_DINF_INTPNT_FACTOR_NUM_FLOPS, 112
MSK_DINF_INTPNT_OPT_STATUS, 108
MSK_DINF_INTPNT_ORDER_TIME, 108
MSK_DINF_INTPNT_PRIMAL_FEAS, 108
MSK_DINF_INTPNT_PRIMAL_OBJ, 108
MSK_DINF_INTPNT_TIME, 108
MSK_DINF_MIO_CLIQUE_SEPARATION_TIME, 109
MSK_DINF_MIO_CMIR_SEPARATION_TIME, 109
MSK_DINF_MIO_CONSTRUCT_SOLUTION_OBJ, 109
MSK_DINF_MIO_DUAL_BOUND_AFTER_PRESOLVE, 110
MSK_DINF_MIO_GMI_SEPARATION_TIME, 110
MSK_DINF_MIO_HEURISTIC_TIME, 109
MSK_DINF_MIO IMPLIED_BOUND_TIME, 110
MSK_DINF_MIO_KNAPSACK_COVER_SEPARATION_TIME,
110
MSK_DINF_MIO_OBJ_ABS_GAP, 109
MSK_DINF_MIO_OBJ_BOUND, 109
MSK_DINF_MIO_OBJ_INT, 109
MSK_DINF_MIO_OBJ_REL_GAP, 109
MSK_DINF_MIO_OPTIMIZER_TIME, 109
MSK_DINF_MIO_PROBING_TIME, 110
MSK_DINF_MIO_ROOT_CUTGEN_TIME, 110
MSK_DINF_MIO_ROOT_OPTIMIZER_TIME, 109
MSK_DINF_MIO_ROOT_PRESOLVE_TIME, 109
MSK_DINF_MIO_TIME, 109
MSK_DINF_MIO_USER_OBJ_CUT, 109
MSK_DINF_OPTIMIZER_TIME, 110
MSK_DINF_PRESOLVE_ELI_TIME, 110
MSK_DINF_PRESOLVE_LINDEP_TIME, 110
MSK_DINF_PRESOLVE_TIME, 110
MSK_DINF_PRIMAL_REPAIR_PENALTY_OBJ, 112
MSK_DINF_QCQO_REFORMULATE_MAX_PERTURBATION,
112
MSK_DINF_QCQO_REFORMULATE_TIME, 112
MSK_DINF_QCQO_REFORMULATE_WORST_CHOLESKY_COLUMN_SCALING,
112
MSK_DINF_QCQO_REFORMULATE_WORST_CHOLESKY_DIAG_SCALING,
112
MSK_DINF_RD_TIME, 110
MSK_DINF_SIM_DUAL_TIME, 109
MSK_DINF_SIM_FEAS, 109
MSK_DINF_SIM_OBJ, 109
MSK_DINF_SIM_PRIMAL_DUAL_TIME, 109
MSK_DINF_SIM_PRIMAL_TIME, 108
MSK_DINF_SIM_TIME, 108
MSK_DINF_SOL_BAS_DUAL_OBJ, 111
MSK_DINF_SOL_BAS_DVIOLCON, 111

MSK_DINF_SOL_BAS_DVIOLVAR, 111
 MSK_DINF_SOL_BAS_NRM_BARX, 111
 MSK_DINF_SOL_BAS_NRM_SLC, 111
 MSK_DINF_SOL_BAS_NRM_SLX, 111
 MSK_DINF_SOL_BAS_NRM_SUC, 111
 MSK_DINF_SOL_BAS_NRM_SUX, 111
 MSK_DINF_SOL_BAS_NRM_XC, 111
 MSK_DINF_SOL_BAS_NRM_XX, 111
 MSK_DINF_SOL_BAS_NRM_Y, 111
 MSK_DINF_SOL_BAS_PRIMAL_OBJ, 111
 MSK_DINF_SOL_BAS_PVIOLCON, 111
 MSK_DINF_SOL_BAS_PVIOLVAR, 111
 MSK_DINF_SOL_ITG_NRM_BARX, 112
 MSK_DINF_SOL_ITG_NRM_XC, 112
 MSK_DINF_SOL_ITG_NRM_XX, 112
 MSK_DINF_SOL_ITG_PRIMAL_OBJ, 111
 MSK_DINF_SOL_ITG_PVIOLBARVAR, 112
 MSK_DINF_SOL_ITG_PVIOLCON, 112
 MSK_DINF_SOL_ITG_PVIOLCONES, 112
 MSK_DINF_SOL_ITG_PVIOLITG, 112
 MSK_DINF_SOL_ITG_PVIOLVAR, 112
 MSK_DINF_SOL_ITR_DUAL_OBJ, 110
 MSK_DINF_SOL_ITR_DVIOLBARVAR, 110
 MSK_DINF_SOL_ITR_DVIOLCON, 110
 MSK_DINF_SOL_ITR_DVIOLCONES, 110
 MSK_DINF_SOL_ITR_DVIOLVAR, 110
 MSK_DINF_SOL_ITR_NRM_BARS, 111
 MSK_DINF_SOL_ITR_NRM_BARX, 111
 MSK_DINF_SOL_ITR_NRM_SLC, 111
 MSK_DINF_SOL_ITR_NRM_SLX, 111
 MSK_DINF_SOL_ITR_NRM_SNX, 111
 MSK_DINF_SOL_ITR_NRM_SUC, 111
 MSK_DINF_SOL_ITR_NRM_SUX, 111
 MSK_DINF_SOL_ITR_NRM_XC, 110
 MSK_DINF_SOL_ITR_NRM_XX, 110
 MSK_DINF_SOL_ITR_NRM_Y, 111
 MSK_DINF_SOL_ITR_PRIMAL_OBJ, 110
 MSK_DINF_SOL_ITR_PVIOLBARVAR, 110
 MSK_DINF_SOL_ITR_PVIOLCON, 110
 MSK_DINF_SOL_ITR_PVIOLCONES, 110
 MSK_DINF_SOL_ITR_PVIOLVAR, 110
 MSK_DINF_TO_CONIC_TIME, 109
 MSKfeaturee, 112
 MSK_FEATURE_PTON, 112
 MSK_FEATURE_PTS, 112
 MSKiinfiteme, 113
 MSK_IINF_ANA_PRO_NUM_CON, 113
 MSK_IINF_ANA_PRO_NUM_CON_EQ, 113
 MSK_IINF_ANA_PRO_NUM_CON_FR, 113
 MSK_IINF_ANA_PRO_NUM_CON_LO, 113
 MSK_IINF_ANA_PRO_NUM_CON_RA, 113
 MSK_IINF_ANA_PRO_NUM_CON_UP, 113
 MSK_IINF_ANA_PRO_NUM_VAR, 113
 MSK_IINF_ANA_PRO_NUM_VAR_BIN, 114
 MSK_IINF_ANA_PRO_NUM_VAR_CONT, 114
 MSK_IINF_ANA_PRO_NUM_VAR_EQ, 113
 MSK_IINF_ANA_PRO_NUM_VAR_FR, 114
 MSK_IINF_ANA_PRO_NUM_VAR_INT, 114
 MSK_IINF_ANA_PRO_NUM_VAR_LO, 113
 MSK_IINF_ANA_PRO_NUM_VAR_RA, 113
 MSK_IINF_ANA_PRO_NUM_VAR_UP, 113
 MSK_IINF_INT_PNT_FACTOR_DIM_DENSE, 114
 MSK_IINF_INT_PNT_ITER, 114
 MSK_IINF_INT_PNT_NUM_THREADS, 116
 MSK_IINF_INT_PNT_SOLVE_DUAL, 114
 MSK_IINF_MIO_ABSGAP_SATISFIED, 115
 MSK_IINF_MIO_CLIQUETABLE_SIZE, 114
 MSK_IINF_MIO_CONSTRUCT_NUM_ROUNDINGS, 114
 MSK_IINF_MIO_CONSTRUCT_SOLUTION, 114
 MSK_IINF_MIO_INITIAL_SOLUTION, 115
 MSK_IINF_MIO_NEAR_ABSGAP_SATISFIED, 115
 MSK_IINF_MIO_NEAR_RELGAP_SATISFIED, 115
 MSK_IINF_MIO_NODE_DEPTH, 114
 MSK_IINF_MIO_NUM_ACTIVE_NODES, 115
 MSK_IINF_MIO_NUM_BRANCH, 115
 MSK_IINF_MIO_NUM_CLIQUETCUTS, 115
 MSK_IINF_MIO_NUM_CMIR_CUTS, 115
 MSK_IINF_MIO_NUM_GOMORY_CUTS, 115
 MSK_IINF_MIO_NUM_IMPLIED_BOUND_CUTS, 115
 MSK_IINF_MIO_NUM_INT_SOLUTIONS, 114
 MSK_IINF_MIO_NUM_KNAPSACK_COVER_CUTS, 115
 MSK_IINF_MIO_NUM_RELAX, 115
 MSK_IINF_MIO_NUM_REPEATED_PREOLVE, 115
 MSK_IINF_MIO_NUMCON, 114
 MSK_IINF_MIO_NUMINT, 114
 MSK_IINF_MIO_NUMVAR, 114
 MSK_IINF_MIO_OBJ_BOUND_DEFINED, 114
 MSK_IINF_MIO_PREOLVED_NUMBIN, 114
 MSK_IINF_MIO_PREOLVED_NUMCON, 114
 MSK_IINF_MIO_PREOLVED_NUMCONT, 114
 MSK_IINF_MIO_PREOLVED_NUMINT, 114
 MSK_IINF_MIO_PREOLVED_NUMVAR, 114
 MSK_IINF_MIO_RELGAP_SATISFIED, 115
 MSK_IINF_MIO_TOTAL_NUM_CUTS, 115
 MSK_IINF_MIO_USER_OBJ_CUT, 115
 MSK_IINF_OPT_NUMCON, 117
 MSK_IINF_OPT_NUMVAR, 117
 MSK_IINF_OPTIMIZE_RESPONSE, 114
 MSK_IINF_RD_NUMBARVAR, 115
 MSK_IINF_RD_NUMCON, 115
 MSK_IINF_RD_NUMCONE, 117
 MSK_IINF_RD_NUMINTVAR, 115
 MSK_IINF_RD_NUMQ, 115
 MSK_IINF_RD_NUMVAR, 115
 MSK_IINF_RD_PROTOTYPE, 115
 MSK_IINF_SIM_DUAL_DEG_ITER, 115
 MSK_IINF_SIM_DUAL_HOTSTART, 116
 MSK_IINF_SIM_DUAL_HOTSTART_LU, 116
 MSK_IINF_SIM_DUAL_INF_ITER, 116
 MSK_IINF_SIM_DUAL_ITER, 116
 MSK_IINF_SIM_NUMCON, 117
 MSK_IINF_SIM_NUMVAR, 117
 MSK_IINF_SIM_PRIMAL_DEG_ITER, 116
 MSK_IINF_SIM_PRIMAL_DUAL_DEG_ITER, 116
 MSK_IINF_SIM_PRIMAL_DUAL_HOTSTART, 116
 MSK_IINF_SIM_PRIMAL_DUAL_HOTSTART_LU, 116

MSK_IINF_SIM_PRIMAL_DUAL_INF_ITER, 116
MSK_IINF_SIM_PRIMAL_DUAL_ITER, 116
MSK_IINF_SIM_PRIMAL_HOTSTART, 116
MSK_IINF_SIM_PRIMAL_HOTSTART_LU, 116
MSK_IINF_SIM_PRIMAL_INF_ITER, 116
MSK_IINF_SIM_PRIMAL_ITER, 116
MSK_IINF_SIM_SOLVE_DUAL, 117
MSK_IINF_SOL_BAS_PROSTA, 116
MSK_IINF_SOL_BAS_SOLSTA, 116
MSK_IINF_SOL_ITG_PROSTA, 116
MSK_IINF_SOL_ITG_SOLSTA, 116
MSK_IINF_SOL_ITR_PROSTA, 116
MSK_IINF_SOL_ITR_SOLSTA, 116
MSK_IINF_STO_NUM_A_REALLOC, 117
MSKinfypee, 117
MSK_INF_DOU_TYPE, 117
MSK_INF_INT_TYPE, 117
MSK_INF_LINT_TYPE, 117
MSKintpntthotstarte, 101
MSK_INTPNT_HOTSTART_DUAL, 101
MSK_INTPNT_HOTSTART_NONE, 101
MSK_INTPNT_HOTSTART_PRIMAL, 101
MSK_INTPNT_HOTSTART_PRIMAL_DUAL, 101
MSKiomodee, 117
MSK_IOMODE_READ, 117
MSK_IOMODE_READWRITE, 117
MSK_IOMODE_WRITE, 117
MSKlanguagee, 99
MSK_LANG_DAN, 99
MSK_LANG_ENG, 99
MSKliinfiteme, 112
MSK_LIINF_BI_CLEAN_DUAL_DEG_ITER, 113
MSK_LIINF_BI_CLEAN_DUAL_ITER, 113
MSK_LIINF_BI_CLEAN_PRIMAL_DEG_ITER, 113
MSK_LIINF_BI_CLEAN_PRIMAL_DUAL_DEG_ITER, 113
MSK_LIINF_BI_CLEAN_PRIMAL_DUAL_ITER, 113
MSK_LIINF_BI_CLEAN_PRIMAL_DUAL_SUB_ITER, 113
MSK_LIINF_BI_CLEAN_PRIMAL_ITER, 113
MSK_LIINF_BI_DUAL_ITER, 112
MSK_LIINF_BI_PRIMAL_ITER, 112
MSK_LIINF_INTPNT_FACTOR_NUM_NZ, 113
MSK_LIINF_MIO_INTPNT_ITER, 112
MSK_LIINF_MIO_PRE SOLVED_ANZ, 112
MSK_LIINF_MIO_SIM_MAXITER_SETBACKS, 113
MSK_LIINF_MIO_SIMPLEX_ITER, 112
MSK_LIINF_RD_NUMANZ, 113
MSK_LIINF_RD_NUMQNZ, 113
MSKmarke, 100
MSK_MARK_LO, 100
MSK_MARK_UP, 100
MSKmiocontsoltypee, 118
MSK_MIO_CONT_SOL_ITG, 118
MSK_MIO_CONT_SOL_ITG_REL, 118
MSK_MIO_CONT_SOL_NONE, 118
MSK_MIO_CONT_SOL_ROOT, 118
MSKmiomodee, 118
MSK_MIO_MODE_IGNORED, 118
MSK_MIO_MODE_SATISFIED, 118
MSKmionodeseltypee, 118
MSK_MIO_NODE_SELECTION_BEST, 118
MSK_MIO_NODE_SELECTION_FIRST, 118
MSK_MIO_NODE_SELECTION_FREE, 118
MSK_MIO_NODE_SELECTION_HYBRID, 118
MSK_MIO_NODE_SELECTION_PSEUDO, 118
MSK_MIO_NODE_SELECTION_WORST, 118
MSKmpsformate, 118
MSK_MPS_FORMAT_CPLEX, 119
MSK_MPS_FORMAT_FREE, 118
MSK_MPS_FORMAT_RELAXED, 118
MSK_MPS_FORMAT_STRICT, 118
MSKmsgkeye, 119
MSK_MSG_MPS_SELECTED, 119
MSK_MSG_READING_FILE, 119
MSK_MSG_WRITING_FILE, 119
MSKnametypee, 107
MSK_NAME_TYPE_GEN, 107
MSK_NAME_TYPE_LP, 107
MSK_NAME_TYPE_MPS, 107
MSKobjsensee, 119
MSK_OBJECTIVE_SENSE_MAXIMIZE, 119
MSK_OBJECTIVE_SENSE_MINIMIZE, 119
MSKonoffkeye, 119
MSK_OFF, 119
MSK_ON, 119
MSKoptimizertypee, 119
MSK_OPTIMIZER_CONIC, 119
MSK_OPTIMIZER_DUAL_SIMPLEX, 119
MSK_OPTIMIZER_FREE, 119
MSK_OPTIMIZER_FREE_SIMPLEX, 119
MSK_OPTIMIZER_INTPNT, 119
MSK_OPTIMIZER_MIXED_INT, 119
MSK_OPTIMIZER_PRIMAL_SIMPLEX, 119
MSKorderingtypee, 119
MSK_ORDER_METHOD_APPMINLOC, 119
MSK_ORDER_METHOD_EXPERIMENTAL, 119
MSK_ORDER_METHOD_FORCE_GRAPHPAR, 120
MSK_ORDER_METHOD_FREE, 119
MSK_ORDER_METHOD_NONE, 120
MSK_ORDER_METHOD_TRY_GRAPHPAR, 119
MSKparametertypee, 120
MSK_PAR_DOU_TYPE, 120
MSK_PAR_INT_TYPE, 120
MSK_PAR_INVALID_TYPE, 120
MSK_PAR_STR_TYPE, 120
MSKpresolvemodee, 120
MSK_PRE SOLVE_MODE_FREE, 120
MSK_PRE SOLVE_MODE_OFF, 120
MSK_PRE SOLVE_MODE_ON, 120
MSKproblemiteme, 120
MSK_PI_CON, 120
MSK_PI_CONE, 120
MSK_PI_VAR, 120
MSKproblemtypee, 120
MSK_PROBTYPE_CONIC, 120

MSK_PROBTYPE_GECO, 120
 MSK_PROBTYPE_LO, 120
 MSK_PROBTYPE_MIXED, 120
 MSK_PROBTYPE_QCQO, 120
 MSK_PROBTYPE_QO, 120
 MSKprostae, 121
 MSK_PRO_STA_DUAL_FEAS, 121
 MSK_PRO_STA_DUAL_INFEAS, 121
 MSK_PRO_STA_ILL_POSED, 121
 MSK_PRO_STA_NEAR_DUAL_FEAS, 121
 MSK_PRO_STA_NEAR_PRIM_AND_DUAL_FEAS, 121
 MSK_PRO_STA_NEAR_PRIM_FEAS, 121
 MSK_PRO_STA_PRIM_AND_DUAL_FEAS, 121
 MSK_PRO_STA_PRIM_AND_DUAL_INFEAS, 121
 MSK_PRO_STA_PRIM_FEAS, 121
 MSK_PRO_STA_PRIM_INFEAS, 121
 MSK_PRO_STA_PRIM_INFEAS_OR_UNBOUNDED, 121
 MSK_PRO_STA_UNKNOWN, 121
 MSKrescodetypee, 121
 MSK_RESPONSE_ERR, 121
 MSK_RESPONSE_OK, 121
 MSK_RESPONSE_TRM, 121
 MSK_RESPONSE_UNK, 121
 MSK_RESPONSE_WRN, 121
 MSKscalingmethode, 122
 MSK_SCALING_METHOD_FREE, 122
 MSK_SCALING_METHOD_POW2, 122
 MSKscalingtypee, 122
 MSK_SCALING_AGGRESSIVE, 122
 MSK_SCALING_FREE, 122
 MSK_SCALING_MODERATE, 122
 MSK_SCALING_NONE, 122
 MSKsensitivitytypee, 122
 MSK_SENSITIVITY_TYPE_BASIS, 122
 MSK_SENSITIVITY_TYPE_OPTIMAL_PARTITION, 122
 MSKsimdegene, 100
 MSK_SIM_DEGEN_AGGRESSIVE, 100
 MSK_SIM_DEGEN_FREE, 100
 MSK_SIM_DEGEN_MINIMUM, 100
 MSK_SIM_DEGEN_MODERATE, 100
 MSK_SIM_DEGEN_NONE, 100
 MSKsimdupvece, 101
 MSK_SIM_EXPLOIT_DUPVEC_FREE, 101
 MSK_SIM_EXPLOIT_DUPVEC_OFF, 101
 MSK_SIM_EXPLOIT_DUPVEC_ON, 101
 MSKsimhotstarte, 101
 MSK_SIM_HOTSTART_FREE, 101
 MSK_SIM_HOTSTART_NONE, 101
 MSK_SIM_HOTSTART_STATUS_KEYS, 101
 MSKsimreforme, 101
 MSK_SIM_REFORMULATION_AGGRESSIVE, 101
 MSK_SIM_REFORMULATION_FREE, 101
 MSK_SIM_REFORMULATION_OFF, 101
 MSK_SIM_REFORMULATION_ON, 101
 MSKsimseltypee, 122
 MSK_SIM_SELECTION_ASE, 122
 MSK_SIM_SELECTION_DEVEX, 122
 MSK_SIM_SELECTION_FREE, 122
 MSK_SIM_SELECTION_FULL, 122
 MSK_SIM_SELECTION_PARTIAL, 122
 MSK_SIM_SELECTION_SE, 122
 MSKsoliteme, 122
 MSK_SOL_ITEM_SLC, 123
 MSK_SOL_ITEM_SLX, 123
 MSK_SOL_ITEM_SNX, 123
 MSK_SOL_ITEM_SUC, 123
 MSK_SOL_ITEM_SUX, 123
 MSK_SOL_ITEM_XC, 122
 MSK_SOL_ITEM_XX, 122
 MSK_SOL_ITEM_Y, 122
 MSKsolstae, 123
 MSK_SOL_STA_DUAL_FEAS, 123
 MSK_SOL_STA_DUAL_ILLPOSED_CER, 123
 MSK_SOL_STA_DUAL_INFEAS_CER, 123
 MSK_SOL_STA_INTEGER_OPTIMAL, 123
 MSK_SOL_STA_NEAR_DUAL_FEAS, 123
 MSK_SOL_STA_NEAR_DUAL_INFEAS_CER, 123
 MSK_SOL_STA_NEAR_INTEGER_OPTIMAL, 123
 MSK_SOL_STA_NEAR_OPTIMAL, 123
 MSK_SOL_STA_NEAR_PRIM_AND_DUAL_FEAS, 123
 MSK_SOL_STA_NEAR_PRIM_FEAS, 123
 MSK_SOL_STA_NEAR_PRIM_INFEAS_CER, 123
 MSK_SOL_STA_OPTIMAL, 123
 MSK_SOL_STA_PRIM_AND_DUAL_FEAS, 123
 MSK_SOL_STA_PRIM_FEAS, 123
 MSK_SOL_STA_PRIM_ILLPOSED_CER, 123
 MSK_SOL_STA_PRIM_INFEAS_CER, 123
 MSK_SOL_STA_UNKNOWN, 123
 MSKsoltypee, 124
 MSK_SOL_BAS, 124
 MSK_SOL_ITG, 124
 MSK_SOL_ITR, 124
 MSKsolveforme, 124
 MSK_SOLVE_DUAL, 124
 MSK_SOLVE_FREE, 124
 MSK_SOLVE_PRIMAL, 124
 MSKstakeye, 124
 MSK_SK_BAS, 124
 MSK_SK_FIX, 124
 MSK_SK_INF, 124
 MSK_SK_LOW, 124
 MSK_SK_SUPBAS, 124
 MSK_SK_UNK, 124
 MSK_SK_UPR, 124
 MSKstartpointtypee, 124
 MSK_STARTING_POINT_CONSTANT, 124
 MSK_STARTING_POINT_FREE, 124
 MSK_STARTING_POINT_GUESS, 124
 MSK_STARTING_POINT_SATISFY_BOUNDS, 124
 MSKstreamtypee, 124
 MSK_STREAM_ERR, 125
 MSK_STREAM_LOG, 125
 MSK_STREAM_MSG, 125
 MSK_STREAM_WRN, 125
 MSKsymmattypee, 107
 MSK_SYMMAT_TYPE_SPARSE, 107

MSKtranspose, 100
MSK_TRANSPOSE_NO, 100
MSK_TRANSPOSE_YES, 100
MSKuploe, 101
MSK_UPLO_LO, 101
MSK_UPLO_UP, 101
MSKvaluee, 125
MSK_LICENSE_BUFFER_LENGTH, 125
MSK_MAX_STR_LEN, 125
MSKvariabletypee, 125
MSK_VAR_TYPE_CONT, 125
MSK_VAR_TYPE_INT, 125
MSKxmlwriteroutputtypee, 121
MSK_WRITE_XML_MODE_COL, 121
MSK_WRITE_XML_MODE_ROW, 121

Functions

Parameters

Double params, 31
MSK_DPAR_ANA_SOL_INFEAS_TOL, 31
MSK_DPAR_BASIS_REL_TOL_S, 31
MSK_DPAR_BASIS_TOL_S, 31
MSK_DPAR_BASIS_TOL_X, 31
MSK_DPAR_CHECK_CONVEXITY_REL_TOL, 31
MSK_DPAR_DATA_SYM_MAT_TOL, 31
MSK_DPAR_DATA_SYM_MAT_TOL_HUGE, 32
MSK_DPAR_DATA_SYM_MAT_TOL_LARGE, 32
MSK_DPAR_DATA_TOL_AIJ, 32
MSK_DPAR_DATA_TOL_AIJ_HUGE, 32
MSK_DPAR_DATA_TOL_AIJ_LARGE, 32
MSK_DPAR_DATA_TOL_BOUND_INF, 32
MSK_DPAR_DATA_TOL_BOUND_WRN, 32
MSK_DPAR_DATA_TOL_C_HUGE, 33
MSK_DPAR_DATA_TOL_CJ_LARGE, 32
MSK_DPAR_DATA_TOL_QIJ, 33
MSK_DPAR_DATA_TOL_X, 33
MSK_DPAR_INTPNT_CO_TOL_DFEAS, 33
MSK_DPAR_INTPNT_CO_TOL_INFEAS, 33
MSK_DPAR_INTPNT_CO_TOL_MU_RED, 33
MSK_DPAR_INTPNT_CO_TOL_NEAR_REL, 33
MSK_DPAR_INTPNT_CO_TOL_PFEAS, 33
MSK_DPAR_INTPNT_CO_TOL_REL_GAP, 34
MSK_DPAR_INTPNT_NL_MERIT_BAL, 34
MSK_DPAR_INTPNT_NL_TOL_DFEAS, 34
MSK_DPAR_INTPNT_NL_TOL_MU_RED, 34
MSK_DPAR_INTPNT_NL_TOL_NEAR_REL, 34
MSK_DPAR_INTPNT_NL_TOL_PFEAS, 34
MSK_DPAR_INTPNT_NL_TOL_REL_GAP, 34
MSK_DPAR_INTPNT_NL_TOL_REL_STEP, 35
MSK_DPAR_INTPNT_QO_TOL_DFEAS, 35
MSK_DPAR_INTPNT_QO_TOL_INFEAS, 35
MSK_DPAR_INTPNT_QO_TOL_MU_RED, 35
MSK_DPAR_INTPNT_QO_TOL_NEAR_REL, 35
MSK_DPAR_INTPNT_QO_TOL_PFEAS, 35
MSK_DPAR_INTPNT_QO_TOL_REL_GAP, 35
MSK_DPAR_INTPNT_TOL_DFEAS, 35
MSK_DPAR_INTPNT_TOL_DSAFE, 36

MSK_DPAR_INTPNT_TOL_INFEAS, 36
MSK_DPAR_INTPNT_TOL_MU_RED, 36
MSK_DPAR_INTPNT_TOL_PATH, 36
MSK_DPAR_INTPNT_TOL_PFEAS, 36
MSK_DPAR_INTPNT_TOL_PSAFE, 36
MSK_DPAR_INTPNT_TOL_REL_GAP, 36
MSK_DPAR_INTPNT_TOL_REL_STEP, 37
MSK_DPAR_INTPNT_TOL_STEP_SIZE, 37
MSK_DPAR_LOWER_OBJ_CUT, 37
MSK_DPAR_LOWER_OBJ_CUT_FINITE_TRH, 37
MSK_DPAR_MIO_DISABLE_TERM_TIME, 37
MSK_DPAR_MIO_MAX_TIME, 37
MSK_DPAR_MIO_NEAR_TOL_ABS_GAP, 38
MSK_DPAR_MIO_NEAR_TOL_REL_GAP, 38
MSK_DPAR_MIO_REL_GAP_CONST, 38
MSK_DPAR_MIO_TOL_ABS_GAP, 38
MSK_DPAR_MIO_TOL_ABS_RELAX_INT, 38
MSK_DPAR_MIO_TOL_FEAS, 38
MSK_DPAR_MIO_TOL_REL_DUAL_BOUND_IMPROVEMENT, 38
MSK_DPAR_MIO_TOL_REL_GAP, 39
MSK_DPAR_OPTIMIZER_MAX_TIME, 39
MSK_DPAR_PREOLVE_TOL_ABS_LINDEP, 39
MSK_DPAR_PREOLVE_TOL_AIJ, 39
MSK_DPAR_PREOLVE_TOL_REL_LINDEP, 39
MSK_DPAR_PREOLVE_TOL_S, 39
MSK_DPAR_PREOLVE_TOL_X, 39
MSK_DPAR_QCQO_REFORMULATE_REL_DROP_TOL, 39
MSK_DPAR_SEMIDEFINITE_TOL_APPROX, 40
MSK_DPAR_SIM_LU_TOL_REL_PIV, 40
MSK_DPAR_SIMPLEX_ABS_TOL_PIV, 40
MSK_DPAR_UPPER_OBJ_CUT, 40
MSK_DPAR_UPPER_OBJ_CUT_FINITE_TRH, 40
Integer params, 40
MSK_IPAR_ANA_SOL_BASIS, 40
MSK_IPAR_ANA_SOL_PRINT_VIOLATED, 40
MSK_IPAR_AUTO_SORT_A_BEFORE_OPT, 41
MSK_IPAR_AUTO_UPDATE_SOL_INFO, 41
MSK_IPAR_BASIS_SOLVE_USE_PLUS_ONE, 41
MSK_IPAR_BI_CLEAN_OPTIMIZER, 41
MSK_IPAR_BI_IGNORE_MAX_ITER, 41
MSK_IPAR_BI_IGNORE_NUM_ERROR, 41
MSK_IPAR_BI_MAX_ITERATIONS, 41
MSK_IPAR_CACHE_LICENSE, 42
MSK_IPAR_CHECK_CONVEXITY, 42
MSK_IPAR_COMPRESS_STATFILE, 42
MSK_IPAR_INFEAS_GENERIC_NAMES, 42
MSK_IPAR_INFEAS_PREFER_PRIMAL, 42
MSK_IPAR_INFEAS_REPORT_AUTO, 42
MSK_IPAR_INFEAS_REPORT_LEVEL, 42
MSK_IPAR_INTPNT_BASIS, 43
MSK_IPAR_INTPNT_DIFF_STEP, 43
MSK_IPAR_INTPNT_HOTSTART, 43
MSK_IPAR_INTPNT_MAX_ITERATIONS, 43
MSK_IPAR_INTPNT_MAX_NUM_COR, 43
MSK_IPAR_INTPNT_MAX_NUM_REFINEMENT_STEPS, 43
MSK_IPAR_INTPNT_MULTI_THREAD, 43

MSK_IPAR_INTPNT_OFF_COL_TRH, 44
 MSK_IPAR_INTPNT_ORDER_METHOD, 44
 MSK_IPAR_INTPNT_REGULARIZATION_USE, 44
 MSK_IPAR_INTPNT_SCALING, 44
 MSK_IPAR_INTPNT_SOLVE_FORM, 44
 MSK_IPAR_INTPNT_STARTING_POINT, 44
 MSK_IPAR_LICENSE_DEBUG, 44
 MSK_IPAR_LICENSE_PAUSE_TIME, 44
 MSK_IPAR_LICENSE_SUPPRESS_EXPIRE_WRNS, 45
 MSK_IPAR_LICENSE_TRH_EXPIRY_WRN, 45
 MSK_IPAR_LICENSE_WAIT, 45
 MSK_IPAR_LOG, 45
 MSK_IPAR_LOG_ANA_PRO, 45
 MSK_IPAR_LOG_BI, 45
 MSK_IPAR_LOG_BI_FREQ, 45
 MSK_IPAR_LOG_CHECK_CONVEXITY, 46
 MSK_IPAR_LOG_CUT_SECOND_OPT, 46
 MSK_IPAR_LOG_EXPAND, 46
 MSK_IPAR_LOG_FACTOR, 46
 MSK_IPAR_LOG_FEAS_REPAIR, 46
 MSK_IPAR_LOG_FILE, 46
 MSK_IPAR_LOG_HEAD, 46
 MSK_IPAR_LOG_INFEAS_ANA, 47
 MSK_IPAR_LOG_INTPNT, 47
 MSK_IPAR_LOG_MIO, 47
 MSK_IPAR_LOG_MIO_FREQ, 47
 MSK_IPAR_LOG_OPTIMIZER, 47
 MSK_IPAR_LOG_ORDER, 47
 MSK_IPAR_LOG_PREOLVE, 47
 MSK_IPAR_LOG_RESPONSE, 48
 MSK_IPAR_LOG_SENSITIVITY, 48
 MSK_IPAR_LOG_SENSITIVITY_OPT, 48
 MSK_IPAR_LOG_SIM, 48
 MSK_IPAR_LOG_SIM_FREQ, 48
 MSK_IPAR_LOG_SIM_MINOR, 48
 MSK_IPAR_LOG_STORAGE, 48
 MSK_IPAR_MAX_NUM_WARNINGS, 49
 MSK_IPAR_MIO_BRANCH_DIR, 49
 MSK_IPAR_MIO_CONSTRUCT_SOL, 49
 MSK_IPAR_MIO_CUT_CLIQUE, 49
 MSK_IPAR_MIO_CUT_CMIR, 49
 MSK_IPAR_MIO_CUT_GMI, 49
 MSK_IPAR_MIO_CUT_IMPLIED_BOUND, 49
 MSK_IPAR_MIO_CUT_KNAPSACK_COVER, 49
 MSK_IPAR_MIO_CUT_SELECTION_LEVEL, 50
 MSK_IPAR_MIO_HEURISTIC_LEVEL, 50
 MSK_IPAR_MIO_MAX_NUM_BRANCHES, 50
 MSK_IPAR_MIO_MAX_NUM_RELAXS, 50
 MSK_IPAR_MIO_MAX_NUM_SOLUTIONS, 50
 MSK_IPAR_MIO_MODE, 50
 MSK_IPAR_MIO_MT_USER_CB, 50
 MSK_IPAR_MIO_NODE_OPTIMIZER, 51
 MSK_IPAR_MIO_NODE_SELECTION, 51
 MSK_IPAR_MIO_PERSPECTIVE_REFORMULATE, 51
 MSK_IPAR_MIO_PROBING_LEVEL, 51
 MSK_IPAR_MIO_RINS_MAX_NODES, 51
 MSK_IPAR_MIO_ROOT_OPTIMIZER, 51
 MSK_IPAR_MIO_ROOT_REPEAT_PREOLVE_LEVEL, 51
 MSK_IPAR_MIO_VB_DETECTION_LEVEL, 52
 MSK_IPAR_MT_SPINCOUNT, 52
 MSK_IPAR_NUM_THREADS, 52
 MSK_IPAR_OPF_MAX_TERMS_PER_LINE, 52
 MSK_IPAR_OPF_WRITE_HEADER, 52
 MSK_IPAR_OPF_WRITE_HINTS, 52
 MSK_IPAR_OPF_WRITE_PARAMETERS, 53
 MSK_IPAR_OPF_WRITE_PROBLEM, 53
 MSK_IPAR_OPF_WRITE_SOL_BAS, 53
 MSK_IPAR_OPF_WRITE_SOL_ITG, 53
 MSK_IPAR_OPF_WRITE_SOL_ITR, 53
 MSK_IPAR_OPF_WRITE_SOLUTIONS, 53
 MSK_IPAR_OPTIMIZER, 53
 MSK_IPAR_PARAM_READ_CASE_NAME, 53
 MSK_IPAR_PARAM_READ_IGN_ERROR, 54
 MSK_IPAR_PREOLVE_ELIMINATOR_MAX_FILL, 54
 MSK_IPAR_PREOLVE_ELIMINATOR_MAX_NUM_TRIES, 54
 MSK_IPAR_PREOLVE_LEVEL, 54
 MSK_IPAR_PREOLVE_LINDEP_ABS_WORK_TRH, 54
 MSK_IPAR_PREOLVE_LINDEP_REL_WORK_TRH, 54
 MSK_IPAR_PREOLVE_LINDEP_USE, 54
 MSK_IPAR_PREOLVE_MAX_NUM_REDUCTIONS, 54
 MSK_IPAR_PREOLVE_USE, 54
 MSK_IPAR_PRIMAL_REPAIR_OPTIMIZER, 55
 MSK_IPAR_READ_DATA_COMPRESSED, 55
 MSK_IPAR_READ_DATA_FORMAT, 55
 MSK_IPAR_READ_DEBUG, 55
 MSK_IPAR_READ_KEEP_FREE_CON, 55
 MSK_IPAR_READ_LP_DROP_NEW_VARS_IN_BOU, 55
 MSK_IPAR_READ_LP_QUOTED_NAMES, 55
 MSK_IPAR_READ_MPS_FORMAT, 55
 MSK_IPAR_READ_MPS_WIDTH, 56
 MSK_IPAR_READ_TASK_IGNORE_PARAM, 56
 MSK_IPAR_SENSITIVITY_ALL, 56
 MSK_IPAR_SENSITIVITY_OPTIMIZER, 56
 MSK_IPAR_SENSITIVITY_TYPE, 56
 MSK_IPAR_SIM_BASIS_FACTOR_USE, 56
 MSK_IPAR_SIM_DEGEN, 56
 MSK_IPAR_SIM_DUAL_CRASH, 57
 MSK_IPAR_SIM_DUAL_PHASEONE_METHOD, 57
 MSK_IPAR_SIM_DUAL_RESTRICT_SELECTION, 57
 MSK_IPAR_SIM_DUAL_SELECTION, 57
 MSK_IPAR_SIM_EXPLOIT_DUPVEC, 57
 MSK_IPAR_SIM_HOTSTART, 57
 MSK_IPAR_SIM_HOTSTART_LU, 57
 MSK_IPAR_SIM_INTEGER, 57
 MSK_IPAR_SIM_MAX_ITERATIONS, 58
 MSK_IPAR_SIM_MAX_NUM_SETBACKS, 58
 MSK_IPAR_SIM_NON_SINGULAR, 58
 MSK_IPAR_SIM_PRIMAL_CRASH, 58
 MSK_IPAR_SIM_PRIMAL_PHASEONE_METHOD, 58
 MSK_IPAR_SIM_PRIMAL_RESTRICT_SELECTION, 58
 MSK_IPAR_SIM_PRIMAL_SELECTION, 59
 MSK_IPAR_SIM_REFACTOR_FREQ, 59
 MSK_IPAR_SIM_REFORMULATION, 59
 MSK_IPAR_SIM_SAVE_LU, 59
 MSK_IPAR_SIM_SCALING, 59

MSK_IPAR_SIM_SCALING_METHOD, 59
MSK_IPAR_SIM_SOLVE_FORM, 59
MSK_IPAR_SIM_STABILITY_PRIORITY, 59
MSK_IPAR_SIM_SWITCH_OPTIMIZER, 60
MSK_IPAR_SOL_FILTER_KEEP_BASIC, 60
MSK_IPAR_SOL_FILTER_KEEP_RANGED, 60
MSK_IPAR_SOL_READ_NAME_WIDTH, 60
MSK_IPAR_SOL_READ_WIDTH, 60
MSK_IPAR_SOLUTION_CALLBACK, 60
MSK_IPAR_TIMING_LEVEL, 60
MSK_IPAR_WRITE_BAS_CONSTRAINTS, 60
MSK_IPAR_WRITE_BAS_HEAD, 61
MSK_IPAR_WRITE_BAS_VARIABLES, 61
MSK_IPAR_WRITE_DATA_COMPRESSED, 61
MSK_IPAR_WRITE_DATA_FORMAT, 61
MSK_IPAR_WRITE_DATA_PARAM, 61
MSK_IPAR_WRITE_FREE_CON, 61
MSK_IPAR_WRITE_GENERIC_NAMES, 61
MSK_IPAR_WRITE_GENERIC_NAMES_IO, 61
MSK_IPAR_WRITE_IGNORE_INCOMPATIBLE_ITEMS, 62
MSK_IPAR_WRITE_INT_CONSTRAINTS, 62
MSK_IPAR_WRITE_INT_HEAD, 62
MSK_IPAR_WRITE_INT_VARIABLES, 62
MSK_IPAR_WRITE_LP_FULL_OBJ, 62
MSK_IPAR_WRITE_LP_LINE_WIDTH, 62
MSK_IPAR_WRITE_LP_QUOTED_NAMES, 62
MSK_IPAR_WRITE_LP_STRICT_FORMAT, 62
MSK_IPAR_WRITE_LP_TERMS_PER_LINE, 63
MSK_IPAR_WRITE_MPS_FORMAT, 63
MSK_IPAR_WRITE_MPS_INT, 63
MSK_IPAR_WRITE_PRECISION, 63
MSK_IPAR_WRITE_SOL_BARVARIABLES, 63
MSK_IPAR_WRITE_SOL_CONSTRAINTS, 63
MSK_IPAR_WRITE_SOL_HEAD, 63
MSK_IPAR_WRITE_SOL_IGNORE_INVALID_NAMES, 63
MSK_IPAR_WRITE_SOL_VARIABLES, 64
MSK_IPAR_WRITE_TASK_INC_SOL, 64
MSK_IPAR_WRITE_XML_MODE, 64
String params, 64
MSK_SPAR_BAS_SOL_FILE_NAME, 64
MSK_SPAR_DATA_FILE_NAME, 64
MSK_SPAR_DEBUG_FILE_NAME, 64
MSK_SPAR_INT_SOL_FILE_NAME, 64
MSK_SPAR_ITR_SOL_FILE_NAME, 64
MSK_SPAR_MIO_DEBUG_STRING, 65
MSK_SPAR_PARAM_COMMENT_SIGN, 65
MSK_SPAR_PARAM_READ_FILE_NAME, 65
MSK_SPAR_PARAM_WRITE_FILE_NAME, 65
MSK_SPAR_READ_MPS_BOU_NAME, 65
MSK_SPAR_READ_MPS_OBJ_NAME, 65
MSK_SPAR_READ_MPS_RAN_NAME, 65
MSK_SPAR_READ_MPS_RHS_NAME, 65
MSK_SPAR_REMOTE_ACCESS_TOKEN, 65
MSK_SPAR_SENSITIVITY_FILE_NAME, 65
MSK_SPAR_SENSITIVITY_RES_FILE_NAME, 66
MSK_SPAR_SOL_FILTER_XC_LOW, 66
MSK_SPAR_SOL_FILTER_XC_UPR, 66

MSK_SPAR_SOL_FILTER_XX_LOW, 66
MSK_SPAR_SOL_FILTER_XX_UPR, 66
MSK_SPAR_STAT_FILE_NAME, 66
MSK_SPAR_STAT_KEY, 66
MSK_SPAR_STAT_NAME, 66
MSK_SPAR_WRITE_LP_GEN_VAR_NAME, 66

Response codes

MSK_RES_OK (*ok*), 78
MSK_RES_TRM_INTERNAL (*trm_internal*), 78
MSK_RES_TRM_INTERNAL_STOP
 (*trm_internal_stop*), 78
MSK_RES_TRM_MAX_ITERATIONS
 (*trm_max_iterations*), 78
MSK_RES_TRM_MAX_NUM_SETBACKS
 (*trm_max_num_setbacks*), 78
MSK_RES_TRM_MAX_TIME (*trm_max_time*), 78
MSK_RES_TRM_MIO_NEAR_ABS_GAP
 (*trm_mio_near_abs_gap*), 78
MSK_RES_TRM_MIO_NEAR_REL_GAP
 (*trm_mio_near_rel_gap*), 78
MSK_RES_TRM_MIO_NUM_BRANCHES
 (*trm_mio_num_branches*), 78
MSK_RES_TRM_MIO_NUM_RELAXS
 (*trm_mio_num_relaxs*), 78
MSK_RES_TRM_NUM_MAX_NUM_INT_SOLUTIONS
 (*trm_num_max_num_int_solutions*),
 79
MSK_RES_TRM_NUMERICAL_PROBLEM
 (*trm_numerical_problem*), 79
MSK_RES_TRM_OBJECTIVE_RANGE
 (*trm_objective_range*), 79
MSK_RES_TRM_STALL (*trm_stall*), 79
MSK_RES_TRM_USER_CALLBACK
 (*trm_user_callback*), 79
MSK_RES_WRN_ANA_ALMOST_INT_BOUNDS
 (*wrn_ana_almost_int_bounds*), 96
MSK_RES_WRN_ANA_C_ZERO (*wrn_ana_c_zero*), 96
MSK_RES_WRN_ANA_CLOSE_BOUNDS
 (*wrn_ana_close_bounds*), 96
MSK_RES_WRN_ANA_EMPTY_COLS
 (*wrn_ana_empty_cols*), 96
MSK_RES_WRN_ANA_LARGE_BOUNDS
 (*wrn_ana_large_bounds*), 96
MSK_RES_WRN_CONSTRUCT_INVALID_SOL_ITG
 (*wrn_construct_invalid_sol_itg*), 96
MSK_RES_WRN_CONSTRUCT_NO_SOL_ITG
 (*wrn_construct_no_sol_itg*), 97
MSK_RES_WRN_CONSTRUCT_SOLUTION_INFEAS
 (*wrn_construct_solution_infeas*), 97
MSK_RES_WRN_DROPPED_NZ_QOBJ
 (*wrn_dropped_nz_qobj*), 97
MSK_RES_WRN_DUPLICATE_BARVARIABLE_NAMES
 (*wrn_duplicate_barvariable_names*), 97
MSK_RES_WRN_DUPLICATE_CONE_NAMES
 (*wrn_duplicate_cone_names*), 97
MSK_RES_WRN_DUPLICATE_CONSTRAINT_NAMES
 (*wrn_duplicate_constraint_names*), 97

MSK_RES_WRN_DUPLICATE_VARIABLE_NAMES (<i>wrn_duplicate_variable_names</i>), 97	MSK_RES_WRN_PARAM_NAME_STR (<i>wrn_param_name_str</i>), 98
MSK_RES_WRN_ELIMINATOR_SPACE (<i>wrn_eliminator_space</i>), 97	MSK_RES_WRN_PARAM_STR_VALUE (<i>wrn_param_str_value</i>), 98
MSK_RES_WRN_EMPTY_NAME (<i>wrn_empty_name</i>), 97	MSK_RES_WRN_PRESOLVE_OUTOFSPACE (<i>wrn_presolve_outofspace</i>), 98
MSK_RES_WRN_IGNORE_INTEGER (<i>wrn_ignore_integer</i>), 97	MSK_RES_WRN_QUAD_CONES_WITH_ROOT_FIXED_AT_ZERO (<i>wrn_quad_cones_with_root_fixed_at_zero</i>), 98
MSK_RES_WRN_INCOMPLETE_LINEAR_DEPENDENCY_CHECK (<i>wrn_incomplete_linear_dependency_check</i>), 97	MSK_RES_WRN_RQUAD_CONES_WITH_ROOT_FIXED_AT_ZERO (<i>wrn_rquad_cones_with_root_fixed_at_zero</i>), 98
MSK_RES_WRN_LARGE_AIJ (<i>wrn_large_aij</i>), 97	MSK_RES_WRN_SOL_FILE_IGNORED_CON (<i>wrn_sol_file_ignored_con</i>), 98
MSK_RES_WRN_LARGE_BOUND (<i>wrn_large_bound</i>), 97	MSK_RES_WRN_SOL_FILE_IGNORED_VAR (<i>wrn_sol_file_ignored_var</i>), 98
MSK_RES_WRN_LARGE_CJ (<i>wrn_large_cj</i>), 97	MSK_RES_WRN_SOL_FILTER (<i>wrn_sol_filter</i>), 99
MSK_RES_WRN_LARGE_CON_FX (<i>wrn_large_con_fx</i>), 97	MSK_RES_WRN_SPAR_MAX_LEN (<i>wrn_spar_max_len</i>), 99
MSK_RES_WRN_LARGE_LO_BOUND (<i>wrn_large_lo_bound</i>), 97	MSK_RES_WRN_SYM_MAT_LARGE (<i>wrn_sym_mat_large</i>), 99
MSK_RES_WRN_LARGE_UP_BOUND (<i>wrn_large_up_bound</i>), 97	MSK_RES_WRN_TOO_FEW_BASIS_VARS (<i>wrn_too_few_basis_vars</i>), 99
MSK_RES_WRN_LICENSE_EXPIRE (<i>wrn_license_expire</i>), 97	MSK_RES_WRN_TOO_MANY_BASIS_VARS (<i>wrn_too_many_basis_vars</i>), 99
MSK_RES_WRN_LICENSE_FEATURE_EXPIRE (<i>wrn_license_feature_expire</i>), 97	MSK_RES_WRN_UNDEF_SOL_FILE_NAME (<i>wrn_undef_sol_file_name</i>), 99
MSK_RES_WRN_LICENSE_SERVER (<i>wrn_license_server</i>), 97	MSK_RES_WRN_USING_GENERIC_NAMES (<i>wrn_using_generic_names</i>), 99
MSK_RES_WRN_LP_DROP_VARIABLE (<i>wrn_lp_drop_variable</i>), 97	MSK_RES_WRN_WRITE_CHANGED_NAMES (<i>wrn_write_changed_names</i>), 99
MSK_RES_WRN_LP_OLD_QUAD_FORMAT (<i>wrn_lp_old_quad_format</i>), 98	MSK_RES_WRN_WRITE_DISCARDED_CFIX (<i>wrn_write_discarded_cfix</i>), 99
MSK_RES_WRN_MIO_INFEASIBLE_FINAL (<i>wrn_mio_infeasible_final</i>), 98	MSK_RES_WRN_ZERO_AIJ (<i>wrn_zero_aij</i>), 99
MSK_RES_WRN_MPS_SPLIT_BOU_VECTOR (<i>wrn_mps_split_bou_vector</i>), 98	MSK_RES_WRN_ZEROS_IN_SPARSE_COL (<i>wrn_zeros_in_sparse_col</i>), 99
MSK_RES_WRN_MPS_SPLIT_RAN_VECTOR (<i>wrn_mps_split_ran_vector</i>), 98	MSK_RES_WRN_ZEROS_IN_SPARSE_ROW (<i>wrn_zeros_in_sparse_row</i>), 99
MSK_RES_WRN_MPS_SPLIT_RHS_VECTOR (<i>wrn_mps_split_rhs_vector</i>), 98	MSK_RES_ERR_AD_INVALID_CODELIST (<i>err_ad_invalid_codelist</i>), 79
MSK_RES_WRN_NAME_MAX_LEN (<i>wrn_name_max_len</i>), 98	MSK_RES_ERR_API_ARRAY_TOO_SMALL (<i>err_api_array_too_small</i>), 79
MSK_RES_WRN_NO_DUALIZER (<i>wrn_no_dualizer</i>), 98	MSK_RES_ERR_API_CB_CONNECT (<i>err_api_cb_connect</i>), 79
MSK_RES_WRN_NO_GLOBAL_OPTIMIZER (<i>wrn_no_global_optimizer</i>), 98	MSK_RES_ERR_API_FATAL_ERROR (<i>err_api_fatal_error</i>), 79
MSK_RES_WRN_NO_NONLINEAR_FUNCTION_WRITE (<i>wrn_no_nonlinear_function_write</i>), 98	MSK_RES_ERR_API_INTERNAL (<i>err_api_internal</i>), 79
MSK_RES_WRN_NZ_IN_UPR_TRI (<i>wrn_nz_in_upr_tri</i>), 98	MSK_RES_ERR_ARG_IS_TOO_LARGE (<i>err_arg_is_too_large</i>), 79
MSK_RES_WRN_OPEN_PARAM_FILE (<i>wrn_open_param_file</i>), 98	MSK_RES_ERR_ARG_IS_TOO_SMALL (<i>err_arg_is_too_small</i>), 79
MSK_RES_WRN_PARAM_IGNORED_CMIO (<i>wrn_param_ignored_cmio</i>), 98	MSK_RES_ERR_ARGUMENT_DIMENSION (<i>err_argument_dimension</i>), 79
MSK_RES_WRN_PARAM_NAME_DOU (<i>wrn_param_name_dou</i>), 98	MSK_RES_ERR_ARGUMENT_IS_TOO_LARGE (<i>err_argument_is_too_large</i>), 79
MSK_RES_WRN_PARAM_NAME_INT (<i>wrn_param_name_int</i>), 98	MSK_RES_ERR_ARGUMENT_LENNEQ (<i>err_argument_lenneq</i>), 79

MSK_RES_ERR_ARGUMENT_PERM_ARRAY (<i>err_argument_perm_array</i>), 79	MSK_RES_ERR_CBF_TOO_MANY_VARIABLES (<i>err_cbf_too_many_variables</i>), 81
MSK_RES_ERR_ARGUMENT_TYPE (<i>err_argument_type</i>), 80	MSK_RES_ERR_CBF_UNSUPPORTED (<i>err_cbf_unsupported</i>), 81
MSK_RES_ERR_BAR_VAR_DIM (<i>err_bar_var_dim</i>), 80	MSK_RES_ERR_CON_Q_NOT_NSD (<i>err_con_q_not_nsd</i>), 81
MSK_RES_ERR_BASIS (<i>err_basis</i>), 80	MSK_RES_ERR_CON_Q_NOT_PSD (<i>err_con_q_not_psd</i>), 81
MSK_RES_ERR_BASIS_FACTOR (<i>err_basis_factor</i>), 80	MSK_RES_ERR_CONE_INDEX (<i>err_cone_index</i>), 81
MSK_RES_ERR_BASIS_SINGULAR (<i>err_basis_singular</i>), 80	MSK_RES_ERR_CONE_OVERLAP (<i>err_cone_overlap</i>), 81
MSK_RES_ERR_BLANK_NAME (<i>err_blank_name</i>), 80	MSK_RES_ERR_CONE_OVERLAP_APPEND (<i>err_cone_overlap_append</i>), 81
MSK_RES_ERR_CANNOT_CLONE_NL (<i>err_cannot_clone_nl</i>), 80	MSK_RES_ERR_CONE_REP_VAR (<i>err_cone_rep_var</i>), 81
MSK_RES_ERR_CANNOT_HANDLE_NL (<i>err_cannot_handle_nl</i>), 80	MSK_RES_ERR_CONE_SIZE (<i>err_cone_size</i>), 81
MSK_RES_ERR_CBF_DUPLICATE_ACOORD (<i>err_cbf_duplicate_acoord</i>), 80	MSK_RES_ERR_CONE_TYPE (<i>err_cone_type</i>), 81
MSK_RES_ERR_CBF_DUPLICATE_BCOORD (<i>err_cbf_duplicate_bcoord</i>), 80	MSK_RES_ERR_CONE_TYPE_STR (<i>err_cone_type_str</i>), 81
MSK_RES_ERR_CBF_DUPLICATE_CON (<i>err_cbf_duplicate_con</i>), 80	MSK_RES_ERR_DATA_FILE_EXT (<i>err_data_file_ext</i>), 81
MSK_RES_ERR_CBF_DUPLICATE_INT (<i>err_cbf_duplicate_int</i>), 80	MSK_RES_ERR_DUP_NAME (<i>err_dup_name</i>), 81
MSK_RES_ERR_CBF_DUPLICATE_OBJ (<i>err_cbf_duplicate_obj</i>), 80	MSK_RES_ERR_DUPLICATE_AIJ (<i>err_duplicate_aij</i>), 81
MSK_RES_ERR_CBF_DUPLICATE_OBJACoord (<i>err_cbf_duplicate_objacoord</i>), 80	MSK_RES_ERR_DUPLICATE_BARVARIABLE_NAMES (<i>err_duplicate_barvariable_names</i>), 82
MSK_RES_ERR_CBF_DUPLICATE_VAR (<i>err_cbf_duplicate_var</i>), 80	MSK_RES_ERR_DUPLICATE_CONE_NAMES (<i>err_duplicate_cone_names</i>), 82
MSK_RES_ERR_CBF_INVALID_CON_TYPE (<i>err_cbf_invalid_con_type</i>), 80	MSK_RES_ERR_DUPLICATE_CONSTRAINT_NAMES (<i>err_duplicate_constraint_names</i>), 82
MSK_RES_ERR_CBF_INVALID_DOMAIN_DIMENSION (<i>err_cbf_invalid_domain_dimension</i>), 80	MSK_RES_ERR_DUPLICATE_VARIABLE_NAMES (<i>err_duplicate_variable_names</i>), 82
MSK_RES_ERR_CBF_INVALID_INT_INDEX (<i>err_cbf_invalid_int_index</i>), 80	MSK_RES_ERR_END_OF_FILE (<i>err_end_of_file</i>), 82
MSK_RES_ERR_CBF_INVALID_VAR_TYPE (<i>err_cbf_invalid_var_type</i>), 80	MSK_RES_ERR_FACTOR (<i>err_factor</i>), 82
MSK_RES_ERR_CBF_NO_VARIABLES (<i>err_cbf_no_variables</i>), 80	MSK_RES_ERR_FEASREPAIR_CANNOT_RELAX (<i>err_feasrepair_cannot_relax</i>), 82
MSK_RES_ERR_CBF_NO_VERSION_SPECIFIED (<i>err_cbf_no_version_specified</i>), 80	MSK_RES_ERR_FEASREPAIR_INCONSISTENT_BOUND (<i>err_feasrepair_inconsistent_bound</i>), 82
MSK_RES_ERR_CBF_OBJ_SENSE (<i>err_cbf_obj_sense</i>), 80	MSK_RES_ERR_FEASREPAIR_SOLVING_RELAXED (<i>err_feasrepair_solving_relaxed</i>), 82
MSK_RES_ERR_CBF_PARSE (<i>err_cbf_parse</i>), 80	MSK_RES_ERR_FILE_LICENSE (<i>err_file_license</i>), 82
MSK_RES_ERR_CBF_SYNTAX (<i>err_cbf_syntax</i>), 81	MSK_RES_ERR_FILE_OPEN (<i>err_file_open</i>), 82
MSK_RES_ERR_CBF_TOO_FEW_CONSTRAINTS (<i>err_cbf_too_few_constraints</i>), 81	MSK_RES_ERR_FILE_READ (<i>err_file_read</i>), 82
MSK_RES_ERR_CBF_TOO_FEW_INTS (<i>err_cbf_too_few_ints</i>), 81	MSK_RES_ERR_FILE_WRITE (<i>err_file_write</i>), 82
MSK_RES_ERR_CBF_TOO_FEW_VARIABLES (<i>err_cbf_too_few_variables</i>), 81	MSK_RES_ERR_FIRST (<i>err_first</i>), 82
MSK_RES_ERR_CBF_TOO_MANY_CONSTRAINTS (<i>err_cbf_too_many_constraints</i>), 81	MSK_RES_ERR_FIRSTI (<i>err_firsti</i>), 82
MSK_RES_ERR_CBF_TOO_MANY_INTS (<i>err_cbf_too_many_ints</i>), 81	MSK_RES_ERR_FIRSTJ (<i>err_firstj</i>), 82
	MSK_RES_ERR_FIXED_BOUND_VALUES (<i>err_fixed_bound_values</i>), 82
	MSK_RES_ERR_FLEXLM (<i>err_flexlm</i>), 82
	MSK_RES_ERR_GLOBAL_INV_CONIC_PROBLEM (<i>err_global_inv_conic_problem</i>), 82
	MSK_RES_ERR_HUGE_AIJ (<i>err_huge_aij</i>), 82
	MSK_RES_ERR_HUGE_C (<i>err_huge_c</i>), 82
	MSK_RES_ERR_IDENTICAL_TASKS (<i>err_identical_tasks</i>), 83
	MSK_RES_ERR_IN_ARGUMENT (<i>err_in_argument</i>), 83

MSK_RES_ERR_INDEX (<i>err_index</i>), 83	MSK_RES_ERR_INV_QOBJ_SUBI
MSK_RES_ERR_INDEX_ARR_IS_TOO_LARGE (<i>err_index_arr_is_too_large</i>), 83	(<i>err_inv_qobj_subi</i>), 84
MSK_RES_ERR_INDEX_ARR_IS_TOO_SMALL (<i>err_index_arr_is_too_small</i>), 83	MSK_RES_ERR_INV_QOBJ_SUBJ
MSK_RES_ERR_INDEX_IS_TOO_LARGE (<i>err_index_is_too_large</i>), 83	(<i>err_inv_qobj_subj</i>), 84
MSK_RES_ERR_INDEX_IS_TOO_SMALL (<i>err_index_is_too_small</i>), 83	MSK_RES_ERR_INV_QOBJ_VAL (<i>err_inv_qobj_val</i>),
MSK_RES_ERR_INF_DOU_INDEX (<i>err_inf_dou_index</i>), 83	84
MSK_RES_ERR_INF_DOU_NAME (<i>err_inf_dou_name</i>), 83	MSK_RES_ERR_INV_SK (<i>err_inv_sk</i>), 84
MSK_RES_ERR_INF_INT_INDEX (<i>err_inf_int_index</i>), 83	MSK_RES_ERR_INV_SK_STR (<i>err_inv_sk_str</i>), 84
MSK_RES_ERR_INF_INT_NAME (<i>err_inf_int_name</i>), 83	MSK_RES_ERR_INV_SKC (<i>err_inv_skc</i>), 84
MSK_RES_ERR_INF_LINT_INDEX (<i>err_inf_lint_index</i>), 83	MSK_RES_ERR_INV_SKN (<i>err_inv_skn</i>), 84
MSK_RES_ERR_INF_LINT_NAME (<i>err_inf_lint_name</i>), 83	MSK_RES_ERR_INV_SKX (<i>err_inv_skc</i>), 84
MSK_RES_ERR_INF_TYPE (<i>err_inf_type</i>), 83	MSK_RES_ERR_INV_VAR_TYPE (<i>err_inv_var_type</i>),
MSK_RES_ERR_INFEAS_UNDEFINED (<i>err_infeas_undefined</i>), 83	84
MSK_RES_ERR_INFINITE_BOUND (<i>err_infinite_bound</i>), 83	MSK_RES_ERR_INVALID_ACCMODE (<i>err_invalid_accmode</i>), 84
MSK_RES_ERR_INT64_TO_INT32_CAST (<i>err_int64_to_int32_cast</i>), 83	MSK_RES_ERR_INVALID_AIJ (<i>err_invalid_aij</i>), 84
MSK_RES_ERR_INTERNAL (<i>err_internal</i>), 83	MSK_RES_ERR_INVALID_AMPL_STUB (<i>err_invalid_ampl_stub</i>), 85
MSK_RES_ERR_INTERNAL_TEST_FAILED (<i>err_internal_test_failed</i>), 83	MSK_RES_ERR_INVALID_BARVAR_NAME (<i>err_invalid_barvar_name</i>), 85
MSK_RES_ERR_INV_APTRE (<i>err_inv_aptre</i>), 83	MSK_RES_ERR_INVALID_COMPRESSION (<i>err_invalid_compression</i>), 85
MSK_RES_ERR_INV_BK (<i>err_inv_bk</i>), 83	MSK_RES_ERR_INVALID_CON_NAME (<i>err_invalid_con_name</i>), 85
MSK_RES_ERR_INV_BKC (<i>err_inv_bkc</i>), 83	MSK_RES_ERR_INVALID_CONE_NAME (<i>err_invalid_cone_name</i>), 85
MSK_RES_ERR_INV_BKX (<i>err_inv_bkx</i>), 83	MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_CONES (<i>err_invalid_file_format_for_cones</i>),
MSK_RES_ERR_INV_CONE_TYPE (<i>err_inv_cone_type</i>), 83	85
MSK_RES_ERR_INV_CONE_TYPE_STR (<i>err_inv_cone_type_str</i>), 84	MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_GENERAL_NL (<i>err_invalid_file_format_for_general_nl</i>),
MSK_RES_ERR_INV_MARKI (<i>err_inv_marki</i>), 84	85
MSK_RES_ERR_INV_MARKJ (<i>err_inv_markj</i>), 84	MSK_RES_ERR_INVALID_FILE_FORMAT_FOR_SYM_MAT (<i>err_invalid_file_format_for_sym_mat</i>),
MSK_RES_ERR_INV_NAME_ITEM (<i>err_inv_name_item</i>), 84	85
MSK_RES_ERR_INV_NUMI (<i>err_inv_numi</i>), 84	MSK_RES_ERR_INVALID_FILE_NAME (<i>err_invalid_file_name</i>), 85
MSK_RES_ERR_INV_NUMJ (<i>err_inv_numj</i>), 84	MSK_RES_ERR_INVALID_FORMAT_TYPE (<i>err_invalid_format_type</i>), 85
MSK_RES_ERR_INV_OPTIMIZER (<i>err_inv_optimizer</i>), 84	MSK_RES_ERR_INVALID_IDX (<i>err_invalid_idx</i>), 85
MSK_RES_ERR_INV_PROBLEM (<i>err_inv_problem</i>),	MSK_RES_ERR_INVALID_IOMODE (<i>err_invalid_iomode</i>), 85
84	MSK_RES_ERR_INVALID_MAX_NUM (<i>err_invalid_max_num</i>), 85
MSK_RES_ERR_INV_QCON_SUBI (<i>err_inv_qcon_subi</i>), 84	MSK_RES_ERR_INVALID_NAME_IN_SOL_FILE (<i>err_invalid_name_in_sol_file</i>), 85
MSK_RES_ERR_INV_QCON_SUBJ (<i>err_inv_qcon_subj</i>), 84	MSK_RES_ERR_INVALID_OBJ_NAME (<i>err_invalid_obj_name</i>), 85
MSK_RES_ERR_INV_QCON_SUBK (<i>err_inv_qcon_subk</i>), 84	MSK_RES_ERR_INVALID_OBJECTIVE_SENSE (<i>err_invalid_objective_sense</i>), 85
MSK_RES_ERR_INV_QCON_VAL (<i>err_inv_qcon_val</i>),	MSK_RES_ERR_INVALID_PROBLEM_TYPE (<i>err_invalid_problem_type</i>), 85
84	MSK_RES_ERR_INVALID_SOL_FILE_NAME (<i>err_invalid_sol_file_name</i>), 85
	MSK_RES_ERR_INVALID_STREAM (<i>err_invalid_stream</i>), 85
	MSK_RES_ERR_INVALID_SURPLUS (<i>err_invalid_surplus</i>), 85

MSK_RES_ERR_INVALID_SYM_MAT_DIM
(*err_invalid_sym_mat_dim*), 85

MSK_RES_ERR_INVALID_TASK (*err_invalid_task*),
85

MSK_RES_ERR_INVALID_UTF8 (*err_invalid_utf8*),
85

MSK_RES_ERR_INVALID_VAR_NAME
(*err_invalid_var_name*), 86

MSK_RES_ERR_INVALID_WCHAR
(*err_invalid_wchar*), 86

MSK_RES_ERR_INVALID_WHICH_SOL
(*err_invalid_whichsol*), 86

MSK_RES_ERR_JSON_DATA (*err_json_data*), 86

MSK_RES_ERR_JSON_FORMAT (*err_json_format*),
86

MSK_RES_ERR_JSON_MISSING_DATA
(*err_json_missing_data*), 86

MSK_RES_ERR_JSON_NUMBER_OVERFLOW
(*err_json_number_overflow*), 86

MSK_RES_ERR_JSON_STRING (*err_json_string*), 86

MSK_RES_ERR_JSON_SYNTAX (*err_json_syntax*), 86

MSK_RES_ERR_LAST (*err_last*), 86

MSK_RES_ERR_LAST_I (*err_lasti*), 86

MSK_RES_ERR_LAST_J (*err_lastj*), 86

MSK_RES_ERR_LAU_ARG_K (*err_lau_arg_k*), 86

MSK_RES_ERR_LAU_ARG_M (*err_lau_arg_m*), 86

MSK_RES_ERR_LAU_ARG_N (*err_lau_arg_n*), 86

MSK_RES_ERR_LAU_ARG_TRANS
(*err_lau_arg_trans*), 86

MSK_RES_ERR_LAU_ARG_TRANSA
(*err_lau_arg_transa*), 86

MSK_RES_ERR_LAU_ARG_TRANSB
(*err_lau_arg_transb*), 86

MSK_RES_ERR_LAU_ARG_UPLO (*err_lau_arg_uplo*),
86

MSK_RES_ERR_LAU_INVALID_LOWER_TRIANGULAR_MATRIX
(*err_lau_invalid_lower_triangular_matrix*),
86

MSK_RES_ERR_LAU_INVALID_SPARSE_SYMMETRIC_MATRIX
(*err_lau_invalid_sparse_symmetric_matrix*),
86

MSK_RES_ERR_LAU_NOT_POSITIVE_DEFINITE
(*err_lau_not_positive_definite*), 86

MSK_RES_ERR_LAU_SINGULAR_MATRIX
(*err_lau_singular_matrix*), 86

MSK_RES_ERR_LAU_UNKNOWN (*err_lau_unknown*),
87

MSK_RES_ERR_LICENSE (*err_license*), 87

MSK_RES_ERR_LICENSE_CANNOT_ALLOCATE
(*err_license_cannot_allocate*), 87

MSK_RES_ERR_LICENSE_CANNOT_CONNECT
(*err_license_cannot_connect*), 87

MSK_RES_ERR_LICENSE_EXPIRED
(*err_license_expired*), 87

MSK_RES_ERR_LICENSE_FEATURE
(*err_license_feature*), 87

MSK_RES_ERR_LICENSE_INVALID_HOSTID
(*err_license_invalid_hostid*), 87

MSK_RES_ERR_LICENSE_MAX (*err_license_max*), 87

MSK_RES_ERR_LICENSE_MOSEKLM_DAEMON
(*err_license_moseklm_daemon*), 87

MSK_RES_ERR_LICENSE_NO_SERVER_LINE
(*err_license_no_server_line*), 87

MSK_RES_ERR_LICENSE_NO_SERVER_SUPPORT
(*err_license_no_server_support*), 87

MSK_RES_ERR_LICENSE_SERVER
(*err_license_server*), 87

MSK_RES_ERR_LICENSE_SERVER_VERSION
(*err_license_server_version*), 87

MSK_RES_ERR_LICENSE_VERSION
(*err_license_version*), 87

MSK_RES_ERR_LINK_FILE_DLL (*err_link_file_dll*),
87

MSK_RES_ERR_LIVING_TASKS (*err_living_tasks*),
87

MSK_RES_ERR_LOWER_BOUND_IS_A_NAN
(*err_lower_bound_is_a_nan*), 87

MSK_RES_ERR_LP_DUP_SLACK_NAME
(*err_lp_dup_slack_name*), 87

MSK_RES_ERR_LP_EMPTY (*err_lp_empty*), 88

MSK_RES_ERR_LP_FILE_FORMAT
(*err_lp_file_format*), 88

MSK_RES_ERR_LP_FORMAT (*err_lp_format*), 88

MSK_RES_ERR_LP_FREE_CONSTRAINT
(*err_lp_free_constraint*), 88

MSK_RES_ERR_LP_INCOMPATIBLE
(*err_lp_incompatible*), 88

MSK_RES_ERR_LP_INVALID_CON_NAME
(*err_lp_invalid_con_name*), 88

MSK_RES_ERR_LP_INVALID_VAR_NAME
(*err_lp_invalid_var_name*), 88

MSK_RES_ERR_LP_WRITE_CONIC_PROBLEM
(*err_lp_write_conic_problem*), 88

MSK_RES_ERR_LP_WRITE_GECO_PROBLEM
(*err_lp_write_geco_problem*), 88

MSK_RES_ERR_LU_MAX_NUM_TRIES
(*err_lu_max_num_tries*), 88

MSK_RES_ERR_MAX_LEN_IS_TOO_SMALL
(*err_max_len_is_too_small*), 88

MSK_RES_ERR_MAXNUMBARVAR
(*err_maxnumbarvar*), 88

MSK_RES_ERR_MAXNUMCON (*err_maxnumcon*), 88

MSK_RES_ERR_MAXNUMCONE (*err_maxnumcone*), 88

MSK_RES_ERR_MAXNUMQNZ (*err_maxnumqnz*), 88

MSK_RES_ERR_MAXNUMVAR (*err_maxnumvar*), 88

MSK_RES_ERR_MIO_INTERNAL (*err_mio_internal*),
88

MSK_RES_ERR_MIO_INVALID_NODE_OPTIMIZER
(*err_mio_invalid_node_optimizer*), 88

MSK_RES_ERR_MIO_INVALID_ROOT_OPTIMIZER
(*err_mio_invalid_root_optimizer*), 88

MSK_RES_ERR_MIO_NO_OPTIMIZER
(*err_mio_no_optimizer*), 88

MSK_RES_ERR_MIO_NOT_LOADED
(*err_mio_not_loaded*), 88

MSK_RES_ERR_MISSING_LICENSE_FILE (<i>err_missing_license_file</i>), 88	MSK_RES_ERR_MUL_A_ELEMENT (<i>err_mul_a_element</i>), 90
MSK_RES_ERR_MIXED_CONIC_AND_NL (<i>err_mixed_conic_and_nl</i>), 88	MSK_RES_ERR_NAME_IS_NULL (<i>err_name_is_null</i>), 90
MSK_RES_ERR_MPS_CONE_OVERLAP (<i>err_mps_cone_overlap</i>), 89	MSK_RES_ERR_NAME_MAX_LEN (<i>err_name_max_len</i>), 90
MSK_RES_ERR_MPS_CONE_REPEAT (<i>err_mps_cone_repeat</i>), 89	MSK_RES_ERR_NAN_IN_BLC (<i>err_nan_in_blc</i>), 90
MSK_RES_ERR_MPS_CONE_TYPE (<i>err_mps_cone_type</i>), 89	MSK_RES_ERR_NAN_IN_BLX (<i>err_nan_in_blx</i>), 90
MSK_RES_ERR_MPS_DUPLICATE_Q_ELEMENT (<i>err_mps_duplicate_q_element</i>), 89	MSK_RES_ERR_NAN_IN_BUC (<i>err_nan_in_buc</i>), 90
MSK_RES_ERR_MPS_FILE (<i>err_mps_file</i>), 89	MSK_RES_ERR_NAN_IN_BUX (<i>err_nan_in_bux</i>), 90
MSK_RES_ERR_MPS_INV_BOUND_KEY (<i>err_mps_inv_bound_key</i>), 89	MSK_RES_ERR_NAN_IN_C (<i>err_nan_in_c</i>), 90
MSK_RES_ERR_MPS_INV_CON_KEY (<i>err_mps_inv_con_key</i>), 89	MSK_RES_ERR_NAN_IN_DOUBLE_DATA (<i>err_nan_in_double_data</i>), 90
MSK_RES_ERR_MPS_INV_FIELD (<i>err_mps_inv_field</i>), 89	MSK_RES_ERR_NEGATIVE_APPEND (<i>err_negative_append</i>), 90
MSK_RES_ERR_MPS_INV_MARKER (<i>err_mps_inv_marker</i>), 89	MSK_RES_ERR_NEGATIVE_SURPLUS (<i>err_negative_surplus</i>), 90
MSK_RES_ERR_MPS_INV_SEC_NAME (<i>err_mps_inv_sec_name</i>), 89	MSK_RES_ERR_NEWER_DLL (<i>err_newer_dll</i>), 90
MSK_RES_ERR_MPS_INV_SEC_ORDER (<i>err_mps_inv_sec_order</i>), 89	MSK_RES_ERR_NO_BARS_FOR_SOLUTION (<i>err_no_bars_for_solution</i>), 90
MSK_RES_ERR_MPS_INVALID_OBJ_NAME (<i>err_mps_invalid_obj_name</i>), 89	MSK_RES_ERR_NO_BARX_FOR_SOLUTION (<i>err_no_barx_for_solution</i>), 90
MSK_RES_ERR_MPS_INVALID_OBJSENSE (<i>err_mps_invalid_objsense</i>), 89	MSK_RES_ERR_NO_BASIS_SOL (<i>err_no_basis_sol</i>), 90
MSK_RES_ERR_MPS_MUL_CON_NAME (<i>err_mps_mul_con_name</i>), 89	MSK_RES_ERR_NO_DUAL_FOR_ITG_SOL (<i>err_no_dual_for_itg_sol</i>), 90
MSK_RES_ERR_MPS_MUL_CSEC (<i>err_mps_mul_csec</i>), 89	MSK_RES_ERR_NO_DUAL_INFEAS_CER (<i>err_no_dual_infeas_cer</i>), 90
MSK_RES_ERR_MPS_MUL_QOBJ (<i>err_mps_mul_qobj</i>), 89	MSK_RES_ERR_NO_INIT_ENV (<i>err_no_init_env</i>), 91
MSK_RES_ERR_MPS_MUL_QSEC (<i>err_mps_mul_qsec</i>), 89	MSK_RES_ERR_NO_OPTIMIZER_VAR_TYPE (<i>err_no_optimizer_var_type</i>), 91
MSK_RES_ERR_MPS_NO_OBJECTIVE (<i>err_mps_no_objective</i>), 89	MSK_RES_ERR_NO_PRIMAL_INFEAS_CER (<i>err_no_primal_infeas_cer</i>), 91
MSK_RES_ERR_MPS_NON_SYMMETRIC_Q (<i>err_mps_non_symmetric_q</i>), 89	MSK_RES_ERR_NO_SNX_FOR_BAS_SOL (<i>err_no_snx_for_bas_sol</i>), 91
MSK_RES_ERR_MPS_NULL_CON_NAME (<i>err_mps_null_con_name</i>), 89	MSK_RES_ERR_NO_SOLUTION_IN_CALLBACK (<i>err_no_solution_in_callback</i>), 91
MSK_RES_ERR_MPS_NULL_VAR_NAME (<i>err_mps_null_var_name</i>), 89	MSK_RES_ERR_NON_UNIQUE_ARRAY (<i>err_non_unique_array</i>), 91
MSK_RES_ERR_MPS_SPLITTED_VAR (<i>err_mps_splitted_var</i>), 89	MSK_RES_ERR_NONCONVEX (<i>err_nonconvex</i>), 91
MSK_RES_ERR_MPS_TAB_IN_FIELD2 (<i>err_mps_tab_in_field2</i>), 90	MSK_RES_ERR_NONLINEAR_EQUALITY (<i>err_nonlinear_equality</i>), 91
MSK_RES_ERR_MPS_TAB_IN_FIELD3 (<i>err_mps_tab_in_field3</i>), 90	MSK_RES_ERR_NONLINEAR_FUNCTIONS_NOT_ALLOWED (<i>err_nonlinear_functions_not_allowed</i>), 91
MSK_RES_ERR_MPS_TAB_IN_FIELD5 (<i>err_mps_tab_in_field5</i>), 90	MSK_RES_ERR_NONLINEAR_RANGED (<i>err_nonlinear_ranged</i>), 91
MSK_RES_ERR_MPS_UNDEF_CON_NAME (<i>err_mps_undef_con_name</i>), 90	MSK_RES_ERR_NR_ARGUMENTS (<i>err_nr_arguments</i>), 91
MSK_RES_ERR_MPS_UNDEF_VAR_NAME (<i>err_mps_undef_var_name</i>), 90	MSK_RES_ERR_NULL_ENV (<i>err_null_env</i>), 91
	MSK_RES_ERR_NULL_POINTER (<i>err_null_pointer</i>), 91
	MSK_RES_ERR_NULL_TASK (<i>err_null_task</i>), 91
	MSK_RES_ERR_NUMCONLIM (<i>err_numconlim</i>), 91
	MSK_RES_ERR_NUMVARLIM (<i>err_numvarlim</i>), 91
	MSK_RES_ERR_OBJ_Q_NOT_NSD (<i>err_obj_q_not_nsd</i>), 91

MSK_RES_ERR_OBJ_Q_NOT_PSD
(*err_obj_q_not_psd*), 91

MSK_RES_ERR_OBJECTIVE_RANGE
(*err_objective_range*), 91

MSK_RES_ERR_OLDER_DLL (*err_older_dll*), 91

MSK_RES_ERR_OPEN_DL (*err_open_dl*), 91

MSK_RES_ERR_OPF_FORMAT (*err_opf_format*), 92

MSK_RES_ERR_OPF_NEW_VARIABLE
(*err_opf_new_variable*), 92

MSK_RES_ERR_OPF_PREMATURE_EOF
(*err_opf_premature_eof*), 92

MSK_RES_ERR_OPTIMIZER_LICENSE
(*err_optimizer_license*), 92

MSK_RES_ERR_OVERFLOW (*err_overflow*), 92

MSK_RES_ERR_PARAM_INDEX (*err_param_index*),
92

MSK_RES_ERR_PARAM_IS_TOO_LARGE
(*err_param_is_too_large*), 92

MSK_RES_ERR_PARAM_IS_TOO_SMALL
(*err_param_is_too_small*), 92

MSK_RES_ERR_PARAM_NAME (*err_param_name*), 92

MSK_RES_ERR_PARAM_NAME_DOU
(*err_param_name_dou*), 92

MSK_RES_ERR_PARAM_NAME_INT
(*err_param_name_int*), 92

MSK_RES_ERR_PARAM_NAME_STR
(*err_param_name_str*), 92

MSK_RES_ERR_PARAM_TYPE (*err_param_type*), 92

MSK_RES_ERR_PARAM_VALUE_STR
(*err_param_value_str*), 92

MSK_RES_ERR_PLATFORM_NOT_LICENSED
(*err_platform_not_licensed*), 92

MSK_RES_ERR_POSTSOLVE (*err_postsolve*), 92

MSK_RES_ERR_PRO_ITEM (*err_pro_item*), 92

MSK_RES_ERR_PROB_LICENSE (*err_prob_license*),
92

MSK_RES_ERR_QCON_SUBI_TOO_LARGE
(*err_qcon_subi_too_large*), 92

MSK_RES_ERR_QCON_SUBI_TOO_SMALL
(*err_qcon_subi_too_small*), 92

MSK_RES_ERR_QCON_UPPER_TRIANGLE
(*err_qcon_upper_triangle*), 92

MSK_RES_ERR_QOBJ_UPPER_TRIANGLE
(*err_qobj_upper_triangle*), 92

MSK_RES_ERR_READ_FORMAT (*err_read_format*),
92

MSK_RES_ERR_READ_LP_MISSING_END_TAG
(*err_read_lp_missing_end_tag*), 93

MSK_RES_ERR_READ_LP_NONEXISTING_NAME
(*err_read_lp_nonexisting_name*),
93

MSK_RES_ERR_REMOVE_CONE_VARIABLE
(*err_remove_cone_variable*), 93

MSK_RES_ERR_REPAIR_INVALID_PROBLEM
(*err_repair_invalid_problem*), 93

MSK_RES_ERR_REPAIR_OPTIMIZATION_FAILED
(*err_repair_optimization_failed*), 93

MSK_RES_ERR_SEN_BOUND_INVALID_LO
(*err_sen_bound_invalid_lo*), 93

MSK_RES_ERR_SEN_BOUND_INVALID_UP
(*err_sen_bound_invalid_up*), 93

MSK_RES_ERR_SEN_FORMAT (*err_sen_format*), 93

MSK_RES_ERR_SEN_INDEX_INVALID
(*err_sen_index_invalid*), 93

MSK_RES_ERR_SEN_INDEX_RANGE
(*err_sen_index_range*), 93

MSK_RES_ERR_SEN_INVALID_REGEX
(*err_sen_invalid_regex*), 93

MSK_RES_ERR_SEN_NUMERICAL
(*err_sen_numerical*), 93

MSK_RES_ERR_SEN_SOLUTION_STATUS
(*err_sen_solution_status*), 93

MSK_RES_ERR_SEN_UNDEF_NAME
(*err_sen_undef_name*), 93

MSK_RES_ERR_SEN_UNHANDLED_PROBLEM_TYPE
(*err_sen_unhandled_problem_type*), 93

MSK_RES_ERR_SERVER_CONNECT
(*err_server_connect*), 93

MSK_RES_ERR_SERVER_PROTOCOL
(*err_server_protocol*), 93

MSK_RES_ERR_SERVER_STATUS
(*err_server_status*), 93

MSK_RES_ERR_SERVER_TOKEN (*err_server_token*),
93

MSK_RES_ERR_SIZE_LICENSE (*err_size_license*),
93

MSK_RES_ERR_SIZE_LICENSE_CON
(*err_size_license_con*), 93

MSK_RES_ERR_SIZE_LICENSE_INTVAR
(*err_size_license_intvar*), 93

MSK_RES_ERR_SIZE_LICENSE_NUMCORES
(*err_size_license_numcores*), 94

MSK_RES_ERR_SIZE_LICENSE_VAR
(*err_size_license_var*), 94

MSK_RES_ERR_SOL_FILE_INVALID_NUMBER
(*err_sol_file_invalid_number*), 94

MSK_RES_ERR_SOLITEM (*err_solitem*), 94

MSK_RES_ERR_SOLVER_PROBTYPE
(*err_solver_probtype*), 94

MSK_RES_ERR_SPACE (*err_space*), 94

MSK_RES_ERR_SPACE_LEAKING
(*err_space_leaking*), 94

MSK_RES_ERR_SPACE_NO_INFO
(*err_space_no_info*), 94

MSK_RES_ERR_SYM_MAT_DUPLICATE
(*err_sym_mat_duplicate*), 94

MSK_RES_ERR_SYM_MAT_HUGE
(*err_sym_mat_huge*), 94

MSK_RES_ERR_SYM_MAT_INVALID
(*err_sym_mat_invalid*), 94

MSK_RES_ERR_SYM_MAT_INVALID_COL_INDEX
(*err_sym_mat_invalid_col_index*), 94

MSK_RES_ERR_SYM_MAT_INVALID_ROW_INDEX
(*err_sym_mat_invalid_row_index*), 94

MSK_RES_ERR_SYM_MAT_INVALID_VALUE (<i>err_sym_mat_invalid_value</i>), 94	MSK_RES_ERR_USER_NLO_FUNC (<i>err_user_nlo_func</i>), 96
MSK_RES_ERR_SYM_MAT_NOT_LOWER_TRINGULAR (<i>err_sym_mat_not_lower_tringular</i>), 94	MSK_RES_ERR_WHICHITEM_NOT_ALLOWED (<i>err_whichitem_not_allowed</i>), 96
MSK_RES_ERR_TASK_INCOMPATIBLE (<i>err_task_incompatible</i>), 94	MSK_RES_ERR_WHICHSOL (<i>err_whichsol</i>), 96
MSK_RES_ERR_TASK_INVALID (<i>err_task_invalid</i>), 94	MSK_RES_ERR_WRITE_LP_FORMAT (<i>err_write_lp_format</i>), 96
MSK_RES_ERR_TASK_WRITE (<i>err_task_write</i>), 94	MSK_RES_ERR_WRITE_LP_NON_UNIQUE_NAME (<i>err_write_lp_non_unique_name</i>), 96
MSK_RES_ERR_THREAD_COND_INIT (<i>err_thread_cond_init</i>), 94	MSK_RES_ERR_WRITE_MPS_INVALID_NAME (<i>err_write_mps_invalid_name</i>), 96
MSK_RES_ERR_THREAD_CREATE (<i>err_thread_create</i>), 94	MSK_RES_ERR_WRITE_OPF_INVALID_VAR_NAME (<i>err_write_opf_invalid_var_name</i>), 96
MSK_RES_ERR_THREAD_MUTEX_INIT (<i>err_thread_mutex_init</i>), 94	MSK_RES_ERR_WRITING_FILE (<i>err_writing_file</i>), 96
MSK_RES_ERR_THREAD_MUTEX_LOCK (<i>err_thread_mutex_lock</i>), 95	MSK_RES_ERR_XML_INVALID_PROBLEM_TYPE (<i>err_xml_invalid_problem_type</i>), 96
MSK_RES_ERR_THREAD_MUTEX_UNLOCK (<i>err_thread_mutex_unlock</i>), 95	MSK_RES_ERR_Y_IS_UNDEFINED (<i>err_y_is_undefined</i>), 96
MSK_RES_ERR_TOCONIC_CONSTR_NOT_CONIC (<i>err_toconic_constr_not_conic</i>), 95	
MSK_RES_ERR_TOCONIC_CONSTR_Q_NOT_PSD (<i>err_toconic_constr_q_not_psd</i>), 95	
MSK_RES_ERR_TOCONIC_CONSTRAINT_FX (<i>err_toconic_constraint_fx</i>), 95	
MSK_RES_ERR_TOCONIC_CONSTRAINT_RA (<i>err_toconic_constraint_ra</i>), 95	
MSK_RES_ERR_TOCONIC_OBJECTIVE_NOT_PSD (<i>err_toconic_objective_not_psd</i>), 95	
MSK_RES_ERR_TOO_SMALL_MAX_NUM_NZ (<i>err_too_small_max_num_nz</i>), 95	
MSK_RES_ERR_TOO_SMALL_MAXNUMANZ (<i>err_too_small_maxnumanz</i>), 95	
MSK_RES_ERR_UNB_STEP_SIZE (<i>err_unb_step_size</i>), 95	
MSK_RES_ERR_UNDEF_SOLUTION (<i>err_undef_solution</i>), 95	
MSK_RES_ERR_UNDEFINED_OBJECTIVE_SENSE (<i>err_undefined_objective_sense</i>), 95	
MSK_RES_ERR_UNHANDLED_SOLUTION_STATUS (<i>err_unhandled_solution_status</i>), 95	
MSK_RES_ERR_UNKNOWN (<i>err_unknown</i>), 95	
MSK_RES_ERR_UPPER_BOUND_IS_A_NAN (<i>err_upper_bound_is_a_nan</i>), 95	
MSK_RES_ERR_UPPER_TRIANGLE (<i>err_upper_triangle</i>), 95	
MSK_RES_ERR_USER_FUNC_RET (<i>err_user_func_ret</i>), 95	
MSK_RES_ERR_USER_FUNC_RET_DATA (<i>err_user_func_ret_data</i>), 95	
MSK_RES_ERR_USER_NLO_EVAL (<i>err_user_nlo_eval</i>), 96	
MSK_RES_ERR_USER_NLO_EVAL_HESSUBI (<i>err_user_nlo_eval_hessubi</i>), 96	
MSK_RES_ERR_USER_NLO_EVAL_HESSUBJ (<i>err_user_nlo_eval_hessubj</i>), 96	